

# Android SDK

4.1.0.0

Generated by Doxygen 1.8.16



<b>1 Seekware Android SDK 4.1</b>	<b>1</b>
<b>2 Seek Hello Example</b>	<b>5</b>
<b>3 Seek Data Example</b>	<b>13</b>
<b>4 Seek Upgrade Example</b>	<b>21</b>
<b>5 Seek Simple Example</b>	<b>29</b>
<b>6 Hierarchical Index</b>	<b>41</b>
6.1 Class Hierarchy . . . . .	41
<b>7 Class Index</b>	<b>43</b>
7.1 Class List . . . . .	43
<b>8 Class Documentation</b>	<b>45</b>
8.1 com.thermal.seekware.SeekCamera.AGCMode Enum Reference . . . . .	45
8.1.1 Detailed Description . . . . .	45
8.1.2 Member Data Documentation . . . . .	45
8.1.2.1 HISTEQ . . . . .	45
8.1.2.2 LEGACY_HISTEQ . . . . .	45
8.1.2.3 LINEAR . . . . .	46
8.2 com.thermal.seekware.SeekCamera.AspectRatio Enum Reference . . . . .	46
8.2.1 Detailed Description . . . . .	46
8.2.2 Member Data Documentation . . . . .	46
8.2.2.1 AUTO . . . . .	47
8.2.2.2 MATCH_HEIGHT . . . . .	48
8.2.2.3 MATCH_WIDTH . . . . .	50
8.3 com.thermal.seekware.SeekCamera.Characteristics Class Reference . . . . .	52
8.3.1 Detailed Description . . . . .	53
8.3.2 Member Function Documentation . . . . .	53
8.3.2.1 convertScreenToSensorPoint() . . . . .	53
8.3.2.2 convertSensorToScreenPoint() . . . . .	53
8.3.2.3 getCorrectedOrientation() . . . . .	54
8.3.2.4 getFirmwareVersion() . . . . .	54
8.3.2.5 getHeight() . . . . .	54
8.3.2.6 getLensFacing() . . . . .	55
8.3.2.7 getModelNumber() . . . . .	55
8.3.2.8 getOrientation() . . . . .	55
8.3.2.9 getSensorOrientation() . . . . .	55
8.3.2.10 getSerialNumber() . . . . .	56
8.3.2.11 getTemperatureUnit() . . . . .	56
8.3.2.12 getWidth() . . . . .	56
8.3.2.13 setLensFacing() . . . . .	56

8.3.2.14 setOrientation()	57
8.3.2.15 setTemperatureUnit()	57
8.4 com.thermal.seekware.SeekCamera.ColorLut Enum Reference	57
8.4.1 Detailed Description	58
8.4.2 Member Function Documentation	58
8.4.2.1 createUserLut()	58
8.4.3 Member Data Documentation	58
8.4.3.1 AMBER	59
8.4.3.2 BLACK_RECON	59
8.4.3.3 BLACKHOT	59
8.4.3.4 GREEN	59
8.4.3.5 HI	60
8.4.3.6 HILO	60
8.4.3.7 IRON	60
8.4.3.8 IRON2	60
8.4.3.9 PRISM	61
8.4.3.10 RECON	61
8.4.3.11 SPECTRA	61
8.4.3.12 TYRIAN	61
8.4.3.13 USER0	62
8.4.3.14 USER1	62
8.4.3.15 USER2	62
8.4.3.16 USER3	62
8.4.3.17 USER4	63
8.4.3.18 WHITEHOT	63
8.5 com.thermal.seekware.SeekIOException.ErrorCode Enum Reference	63
8.5.1 Detailed Description	63
8.5.2 Member Function Documentation	63
8.5.2.1 contains()	63
8.5.2.2 get()	64
8.5.2.3 value()	64
8.6 com.thermal.seekware.SeekPipelineException.ErrorCode Enum Reference	64
8.6.1 Detailed Description	65
8.6.2 Member Function Documentation	65
8.6.2.1 contains()	65
8.6.2.2 get()	65
8.6.2.3 value()	66
8.7 com.thermal.seekware.SeekCamera.LensFacing Enum Reference	66
8.7.1 Detailed Description	66
8.7.2 Member Data Documentation	66
8.7.2.1 BACK	66
8.7.2.2 FRONT	67

8.8 com.thermal.seekware.SeekCamera.MemoryRegion Enum Reference	67
8.8.1 Detailed Description	67
8.8.2 Member Data Documentation	67
8.8.2.1 IMAGE0	67
8.8.2.2 IMAGE1	67
8.8.2.3 NEW_IMAGE	68
8.9 com.thermal.seekware.Thermography.Metrics Class Reference	68
8.9.1 Detailed Description	68
8.9.2 Member Function Documentation	68
8.9.2.1 getAverage()	68
8.9.2.2 getMax()	69
8.9.2.3 getMin()	69
8.10 com.thermal.seekware.SeekImageView.OnFrameAvailableListener Interface Reference	69
8.10.1 Detailed Description	69
8.10.2 Member Function Documentation	69
8.10.2.1 onFrameAvailable()	69
8.11 com.thermal.seekware.SeekImageReader.OnImageAvailableListener Interface Reference	70
8.11.1 Detailed Description	70
8.11.2 Member Function Documentation	70
8.11.2.1 onImageAvailable()	70
8.12 com.thermal.seekware.SeekCamera.Orientation Enum Reference	71
8.12.1 Detailed Description	71
8.12.2 Member Function Documentation	71
8.12.2.1 getCorrectedOrientation()	71
8.12.2.2 next()	72
8.12.2.3 previous()	72
8.12.3 Member Data Documentation	72
8.12.3.1 ORIENTATION_0	72
8.12.3.2 ORIENTATION_180	72
8.12.3.3 ORIENTATION_270	72
8.12.3.4 ORIENTATION_90	73
8.13 com.thermal.seekware.SeekUtility.OrientationManager Class Reference	73
8.13.1 Detailed Description	73
8.13.2 Member Function Documentation	73
8.13.2.1 addViews()	73
8.13.2.2 getOrientation()	74
8.13.2.3 getRawOrientation()	74
8.14 com.thermal.seekware.SeekUtility.PermissionHandler.Permission Enum Reference	74
8.14.1 Detailed Description	74
8.15 com.thermal.seekware.SeekUtility.PermissionHandler Class Reference	74
8.15.1 Detailed Description	75
8.16 com.thermal.seekware.SeekCamera Class Reference	75

8.16.1 Detailed Description	76
8.16.2 Member Function Documentation	77
8.16.2.1 close()	78
8.16.2.2 createSeekCameraCaptureSession() [1/2]	78
8.16.2.3 createSeekCameraCaptureSession() [2/2]	78
8.16.2.4 getAspectRatio()	78
8.16.2.5 getCharacteristics()	79
8.16.2.6 getChipId()	79
8.16.2.7 getColorLut()	79
8.16.2.8 getColorLutName()	79
8.16.2.9 getColorPalette() [1/2]	80
8.16.2.10 getColorPalette() [2/2]	80
8.16.2.11 getCurrentState()	80
8.16.2.12 getEmissivity()	80
8.16.2.13 getImageSmoothing()	81
8.16.2.14 loadUserLutData()	81
8.16.2.15 memoryRead() [1/2]	81
8.16.2.16 memoryRead() [2/2]	82
8.16.2.17 memoryWrite() [1/2]	82
8.16.2.18 memoryWrite() [2/2]	83
8.16.2.19 open()	83
8.16.2.20 reboot()	84
8.16.2.21 resumeShutter()	84
8.16.2.22 setAGCMode()	84
8.16.2.23 setAspectRatio()	84
8.16.2.24 setColorLut()	85
8.16.2.25 setEmissivity()	85
8.16.2.26 setImageSmoothing()	85
8.16.2.27 setSeekExceptionListener()	85
8.16.2.28 start()	86
8.16.2.29 stop()	86
8.16.2.30 suspendShutter()	86
8.16.2.31 toString()	86
8.16.2.32 triggerShutter()	87
8.16.2.33 upgradeFirmware() [1/2]	87
8.16.2.34 upgradeFirmware() [2/2]	87
8.17 com.thermal.seekware.SeekCameraManager Class Reference	87
8.17.1 Detailed Description	88
8.17.2 Constructor & Destructor Documentation	88
8.17.2.1 SeekCameraManager()	88
8.17.3 Member Function Documentation	88
8.17.3.1 getUSBDeviceCount()	89

8.17.4 Member Data Documentation	89
8.17.4.1 context	89
8.18 com.thermal.seekware.SeekCamera.SeekExceptionListener Interface Reference	89
8.18.1 Detailed Description	89
8.18.2 Member Function Documentation	89
8.18.2.1 onSeekIOException()	89
8.19 com.thermal.seekware.SeekImage Class Reference	90
8.19.1 Detailed Description	90
8.19.2 Member Function Documentation	90
8.19.2.1 getColorBitmap()	90
8.19.2.2 getColorsUsed()	91
8.19.2.3 getFilteredBuffer()	91
8.19.2.4 getThermography()	91
8.20 com.thermal.seekware.SeekImageReader Class Reference	91
8.20.1 Detailed Description	92
8.20.2 Constructor & Destructor Documentation	92
8.20.2.1 SeekImageReader() [1/2]	92
8.20.2.2 SeekImageReader() [2/2]	92
8.20.3 Member Function Documentation	92
8.20.3.1 onImageSent()	93
8.20.3.2 setOnImageAvailableListener()	93
8.21 com.thermal.seekware.SeekImageView Class Reference	93
8.21.1 Detailed Description	94
8.21.2 Constructor & Destructor Documentation	94
8.21.2.1 SeekImageView() [1/3]	94
8.21.2.2 SeekImageView() [2/3]	94
8.21.2.3 SeekImageView() [3/3]	95
8.21.3 Member Function Documentation	95
8.21.3.1 onImageSent()	95
8.21.3.2 setInput()	95
8.21.3.3 setFrameAvailableListener()	96
8.22 com.thermal.seekware.SeekIOException Class Reference	96
8.22.1 Detailed Description	96
8.23 com.thermal.seekware.SeekLogger Class Reference	96
8.23.1 Detailed Description	97
8.23.2 Member Function Documentation	97
8.23.2.1 addTagFilters()	97
8.23.2.2 debug()	97
8.23.2.3 error()	97
8.23.2.4 info()	98
8.23.2.5 setFilter()	98
8.23.2.6 verbose()	98

8.23.2.7 warn()	99
8.23.3 Member Data Documentation	99
8.23.3.1 ALL	99
8.23.3.2 NONE	99
8.24 com.thermal.seekware.SeekPipeline Class Reference	100
8.24.1 Detailed Description	100
8.24.2 Member Function Documentation	100
8.24.2.1 onImageSent()	100
8.24.3 Member Data Documentation	101
8.24.3.1 image	101
8.24.3.2 input	101
8.25 com.thermal.seekware.SeekPipelineException Class Reference	101
8.25.1 Detailed Description	102
8.25.2 Member Function Documentation	102
8.25.2.1 getErrorCode()	102
8.26 com.thermal.seekware.SeekPipelineListener Interface Reference	102
8.26.1 Detailed Description	102
8.26.2 Member Function Documentation	102
8.26.2.1 onImageSent()	102
8.27 com.thermal.seekware.SeekUtility Class Reference	103
8.27.1 Detailed Description	104
8.27.2 Member Function Documentation	104
8.27.2.1 allocateByteBuffer()	104
8.27.2.2 bitmapFromUri()	104
8.27.2.3 byteArrayFromFile()	104
8.27.2.4 byteBufferFromFile()	105
8.27.2.5 closest()	105
8.27.2.6 createSquaredBitmap()	106
8.27.2.7 createVideoThumbnail()	106
8.27.2.8 distance()	106
8.27.2.9 enumNameToString()	107
8.27.2.10 findFirmwareUpgradeFiles()	107
8.27.2.11 flipBitmapHorizontal()	108
8.27.2.12 flipBitmapVertical()	108
8.27.2.13 generateFilename()	108
8.27.2.14 getBitmapFromDrawable()	108
8.27.2.15 getDeviceDefaultOrientation()	109
8.27.2.16 overlayBitmapToCenter()	109
8.27.2.17 resizeBitmap()	109
8.27.2.18 rotateBitmap()	110
8.27.2.19 saveByteArray()	110
8.27.2.20 saveByteBufferAsPrivateRaw()	110



8.28 com.thermal.seekware.SeekCamera.State Enum Reference	111
8.28.1 Detailed Description	111
8.28.2 Member Function Documentation	111
8.28.2.1 isAtLeast()	111
8.28.3 Member Data Documentation	112
8.28.3.1 CLOSED	112
8.28.3.2 INITIALIZED	112
8.28.3.3 OPENED	112
8.28.3.4 STARTED	112
8.28.3.5 STOPPED	112
8.29 com.thermal.seekware.SeekUtility.PermissionHandler.StateCallback Interface Reference	113
8.29.1 Detailed Description	113
8.30 com.thermal.seekware.SeekCamera.StateCallback Interface Reference	113
8.30.1 Detailed Description	113
8.30.2 Member Function Documentation	113
8.30.2.1 onClosed()	113
8.30.2.2 onError()	114
8.30.2.3 onInitialized()	114
8.30.2.4 onMemoryAccess()	114
8.30.2.5 onOpened()	115
8.30.2.6 onReboot()	115
8.30.2.7 onStarted()	115
8.30.2.8 onStopped()	115
8.31 com.thermal.seekware.SeekUtility.Temperature Class Reference	116
8.31.1 Detailed Description	116
8.31.2 Constructor & Destructor Documentation	116
8.31.2.1 Temperature() [1/2]	116
8.31.2.2 Temperature() [2/2]	117
8.31.3 Member Function Documentation	117
8.31.3.1 getUnit()	117
8.31.3.2 getValue()	117
8.31.3.3 setUnit()	117
8.32 com.thermal.seekware.Thermography Class Reference	118
8.32.1 Detailed Description	118
8.32.2 Member Function Documentation	119
8.32.2.1 calcAreaMetrics()	119
8.32.2.2 calcAreaTemperature()	119
8.32.2.3 calcSpotMetrics()	120
8.32.2.4 calcSpotTemperature()	120
8.32.2.5 calculateIndex()	121
8.32.2.6 fromFile()	122
8.32.2.7 fromShort()	122

---

8.32.2.8 getBuffer()	122
8.32.2.9 getMaxPoint()	123
8.32.2.10 getMaxTemp()	123
8.32.2.11 getMinPoint()	123
8.32.2.12 getMinTemp()	124
8.32.2.13 getPointTemperature()	124
8.32.2.14 getSpotTemp()	124
8.32.3 Member Data Documentation	124
8.32.3.1 THERMOGRAPHY_OFFSET	125
8.32.3.2 THERMOGRAPHY_SCALE	125
8.33 com.thermal.seekware.SeekUtility.Temperature.Unit Enum Reference	125
8.33.1 Detailed Description	125
8.33.2 Member Data Documentation	125
8.33.2.1 CELSIUS	125
8.33.2.2 FAHRENHEIT	125
8.33.2.3 KELVIN	125
<b>Index</b>	<b>127</b>

## Chapter 1

# Seekware Android SDK 4.1

### Welcome

The Seek Thermal Android SDK was created for developers who want to use Seek Thermal cameras in their own products. The SDK is designed to be simple to use while also providing access to key capabilities of the camera. We offer the Seek Thermal Android SDK for multiple platforms with a common API.

### Supported Cameras

Table 1.1 Figure 1 - Supported Ca



Figure 1.1 Compact




Figure 1.3 Starter Kit

**Table 1.2 Figure 2 - Supported Platforms**

Camera	Image	Speed
Compact PIR-206	206 x 156	< 9Hz
CompactXR PIR-206	206 x 156	< 9Hz
Compact Pro PIR-320	320 x 240	< 9Hz
Compact Pro FF PIR-320	320 x 240	< 18Hz
J2/C2x/SK2x PIR-206	206 x 156	< 18Hz
J3/C3x/SK3x PIR-320	320 x 240	< 18Hz

NOTE: Starter Kits that run at higher frame rates are available on special request.

## Seek Thermal SDK API

The class structure of the SDK is modelled after the Android Camera2 API as follows:

**Table 1.3 Figure 3 Seekware/Camera2 Class API**

Seekware Class	Camera2 Class
<a href="#">SeekCameraManager</a>	CameraManager
<a href="#">SeekCamera</a>	CameraDevice
SeekCameraCaptureSession	CameraCaptureSession
<a href="#">SeekImageView</a>	TextureView/SurfaceView/ImageView

## SDK Class Relationship Diagram

---




Figure 1.5 Class Relationships

## SDK Examples

The Seek Thermal Android Software Development Kit (SDK) contains four examples to help you get started:

1. [Seek Hello Example](#)

2. [Seek Data Example](#)
3. [Seek Upgrade Example](#)
4. [Seek Simple Example](#)

## SDK 4.1 Release Notes

1. Initial public release
  - Includes cross platform library for USB communication
  - Supports Firmware upgrade functionality
2. Known Bugs/Limitations:
  - No support for Localization strings

## Attributions:

- Settings Icon made by Gregor Cresnar from <https://www.flaticon.com>
- Info Icon from [https://en.wikipedia.org/wiki/File:Infobox\\_info\\_icon.svg](https://en.wikipedia.org/wiki/File:Infobox_info_icon.svg)

## Build Tools

- Android Studio 3.5.1
- Android 10.0 (Q) API 29
- Android NDK r16b
- Gradle wrapper 5.1.1
- Gradle build tools 3.4.1
- Android SDK Tools 29.0.2
- AndroidX appcompat:appcompat:1.1.0
- AndroidX legacy-preference-v14:1.0.0
- AndroidX constraintlayout:1.1.3
- AndroidX lifecycle-runtime:2.1.0
- AndroidX lifecycle-extensions:2.1.0
- AndroidX vectordrawable:vectordrawable:1.0.1

## Chapter 2

# Seek Hello Example


This tutorial shows you how to create a new Hello World Android project with Android Studio and the Seek Thermal Android SDK.

1. Create the Android Studio project
2. Change the AndroidManifest.xml file
3. Add Seek Android SDK to project
4. Create the User Interface
5. Write the MainActivity.java code
6. Application Screenshot

### Create the Android Studio project

To create your new Android project, follow these steps:


1. In the Welcome to Android Studio window, click Start a new Android Studio project or if you have a project already opened, select File > New > New Project.
2. In the Choose your project window, select Empty Activity and click Next.



**Figure 2.1 New Project**

3. In the Configure your project window, complete the following:





**Figure 2.2 Configure Project**

- Enter "Seek Hello" in the Name field.
- Enter "com.example.seekhello" in the Package name field.
- If you'd like to place the project in a different folder, change its Save location.
- Select Java from the Language drop-down menu.
- Select the checkbox next to Use androidx.\* artifacts.
- Click Finish.

## Change the AndroidManifest.xml file

Insert the following USB Device Intents to the AndroidManifest.xml file for ".MainActivity":

```
<activity android:name=".MainActivity">
  <intent-filter>
    <action android:name="android.intent.action.MAIN" />
    <category android:name="android.intent.category.LAUNCHER" />
    <action android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED" />
  </intent-filter>
  <meta-data android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED"
    android:resource="@xml/seekware_device_filter" />
</activity>
```

## Add Seek Android SDK to project

The Seek Thermal Android SDK is delivered as an AAR (Android Archive) for use with Android Studio and Gradle.

1. Open up the project structure by right-clicking on your project and choosing "Open Module Settings" or choosing "File" > "Project Structure..."
2. Click the "+" button in the top left to add a new module.
3. Choose "Import .JAR or .AAR Package" and click the "Next" button.
4. Find your file using the ellipsis button ("...") beside the "File name" field. Studio will automatically create a subproject name. Click "Finish".
5. Gradle will sync, which may take a few minutes. Add the new module as a dependency to your app. In the "Project Structure..." window, a new module has appeared representing the SDK. Keep the app's module selected and click on the Dependencies pane.
6. Use the "+" button at the bottom of the dependencies screen, and choose "module dependency". The dependencies screen is quite tall, so this button might be invisible at first.
7. The screen that pops up should show the Seekware\_Android\_4.0. Click "OK".

## Create the User Interface for the Application:

Overwrite the `res/layout/activity_main.xml` file:




Figure 2.3 User Interface

```
<?xml version="1.0" encoding="utf-8"?>
<androidx.constraintlayout.widget.ConstraintLayout
    xmlns:android="http://schemas.android.com/apk/res/android"
    xmlns:app="http://schemas.android.com/apk/res-auto"
    xmlns:tools="http://schemas.android.com/tools"
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    tools:context=".MainActivity">
    <com.thermal.seekware.SeekImageView
        android:id="@+id/seek_preview"
        android:layout_width="0dp"
        android:layout_height="0dp"
        app:layout_constraintDimensionRatio="H, 3:4"
        app:layout_constraintEnd_toEndOf="parent"
        app:layout_constraintStart_toStartOf="parent"
        app:layout_constraintTop_toTopOf="parent" />
    <LinearLayout
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        app:layout_constraintTop_toBottomOf="@id/seek_preview"
        app:layout_constraintBottom_toBottomOf="parent"
        app:layout_constraintStart_toStartOf="parent"
        app:layout_constraintEnd_toEndOf="parent">
        <TextView
            android:id="@+id/camera_info"
            android:layout_width="wrap_content"
            android:layout_height="wrap_content"
```

```

        android:textColor="#000000"
        android:gravity="center" />
    </LinearLayout>
</androidx.constraintlayout.widget.ConstraintLayout>

```

## Write the MainActivity.java code

Add the following handlers to the MainActivity.java source file:

```

import android.content.pm.ActivityInfo;
import androidx.appcompat.app.AppCompatActivity;
import android.os.Bundle;
import android.widget.TextView;
import com.thermal.seekware.SeekCamera;
import com.thermal.seekware.SeekCameraManager;
import com.thermal.seekware.SeekImageView;
import com.thermal.seekware.SeekLogger;
public class MainActivity extends AppCompatActivity {
    private TextView cameraInfo;
    private SeekCameraManager seekCameraManager;
    private SeekImageView seekImageView;
    private SeekCamera.StateCallback stateCallback = new SeekCamera.StateCallback() {
        @Override
        public void onInitialized(SeekCamera seekCamera) {
        }
        @Override
        public void onOpened(SeekCamera seekCamera) {
            seekCamera.createSeekCameraCaptureSession(seekImageView);
        }
        @Override
        public void onStarted(SeekCamera seekCamera) {
            seekCamera.setColorLut(SeekCamera.ColorLut.TYRIAN);
            cameraInfo.setText(seekCamera.toString());
        }
        @Override
        public void onStopped(SeekCamera seekCamera) {
            cameraInfo.setText("");
        }
        @Override
        public void onClosed(SeekCamera seekCamera) {
        }
        @Override
        public void onMemoryAccess(SeekCamera camera, SeekCamera.MemoryRegion region, int progress){
            SeekLogger.debug("Main Activity", "SeekCamera Memory Read Progress: " + progress);
        }
        @Override
        public void onError(SeekCamera seekCamera, Exception e) {
        }
    };
    @Override
    protected void onCreate(Bundle savedInstanceState) {
        super.onCreate(savedInstanceState);
        setContentView(R.layout.activity_main);
        setRequestedOrientation(ActivityInfo.SCREEN_ORIENTATION_PORTRAIT);
        cameraInfo = findViewById(R.id.camera_info);
        seekImageView = findViewById(R.id.seek_preview);
        seekCameraManager = new SeekCameraManager(this, null, stateCallback);
    }
}

```

## Application Screenshot

Here is a screenshot of the completed application:




Figure 2.4 Screenshot



## Chapter 3

# Seek Data Example


This example shows you how to create an application to read data from a Seek Thermal Camera with Android Studio and the Seek Thermal Android SDK.

1. Create the Android Studio project
2. Change the AndroidManifest.xml file
3. Add Seek Android SDK to project
4. Create the User Interface
5. Write the MainActivity.java code
6. Application Screenshot

### Create the Android Studio project

To create your new Android project, follow these steps:


1. In the Welcome to Android Studio window, click Start a new Android Studio project or if you have a project already opened, select File > New > New Project.
2. In the Choose your project window, select Empty Activity and click Next.



**Figure 3.1 New Project**

3. In the Configure your project window, complete the following:





**Figure 3.2 Configure Project**

- Enter "Seek Data" in the Name field.
- Enter "com.example.seekdata" in the Package name field.
- If you'd like to place the project in a different folder, change its Save location.
- Select Java from the Language drop-down menu.
- Select the checkbox next to Use androidx.\* artifacts.
- Click Finish.

## Change the AndroidManifest.xml file

Insert the following USB Device Intents to the AndroidManifest.xml file for ".MainActivity":

```
<activity android:name=".MainActivity">
  <intent-filter>
    <action android:name="android.intent.action.MAIN" />
    <category android:name="android.intent.category.LAUNCHER" />
    <action android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED" />
  </intent-filter>
  <meta-data android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED"
    android:resource="@xml/seekware_device_filter" />
</activity>
```


## Add Seek Android SDK to project

The Seek Thermal Android SDK is delivered as an AAR (Android Archive) for use with Android Studio and Gradle.

1. Open up the project structure by right-clicking on your project and choosing "Open Module Settings" or choosing "File" > "Project Structure..."
2. Click the "+" button in the top left to add a new module.
3. Choose "Import .JAR or .AAR Package" and click the "Next" button.
4. Find your file using the ellipsis button ("...") beside the "File name" field. Studio will automatically create a subproject name. Click "Finish".
5. Gradle will sync, which may take a few minutes. Add the new module as a dependency to your app. In the "Project Structure..." window, a new module has appeared representing the SDK. Keep the app's module selected and click on the Dependencies pane.
6. Use the "+" button at the bottom of the dependencies screen, and choose "module dependency". The dependencies screen is quite tall, so this button might be invisible at first.
7. The screen that pops up should show the Seekware\_Android\_4.0. Click "OK".

## Create the User Interface for the Application:

Overwrite the res/layout/activity\_main.xml file:



**Figure 3.3 User Interface**

```
<?xml version="1.0" encoding="utf-8"?>
<androidx.constraintlayout.widget.ConstraintLayout
    xmlns:android="http://schemas.android.com/apk/res/android"
    xmlns:app="http://schemas.android.com/apk/res-auto"
    xmlns:tools="http://schemas.android.com/tools"
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    tools:context=".MainActivity">
    <TextView
        android:id="@+id/thermography_info"
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:gravity="center"
        app:layout_constraintBottom_toBottomOf="parent"
        app:layout_constraintLeft_toLeftOf="parent"
        app:layout_constraintRight_toRightOf="parent"
        app:layout_constraintTop_toTopOf="parent" />
</androidx.constraintlayout.widget.ConstraintLayout>
```

## Write the MainActivity.java code

Add the following handlers to the MainActivity.java source file:


```

package com.example.seekdata;
import androidx.appcompat.app.AppCompatActivity;
import android.os.Bundle;
import android.widget.TextView;
import com.thermal.seekware.SeekCamera;
import com.thermal.seekware.SeekCameraManager;
import com.thermal.seekware.SeekImage;
import com.thermal.seekware.SeekImageReader;
import com.thermal.seekware.SeekLogger;
public class MainActivity extends AppCompatActivity implements SeekImageReader.OnImageAvailableListener {
    private TextView thermographyInfo;
    private SeekCamera seekCamera;
    private SeekCameraManager seekCameraManager;
    private SeekImageReader seekImageReader;
    private SeekCamera.StateCallback stateCallback = new SeekCamera.StateCallback() {
        @Override
        public void onInitialized(SeekCamera seekCamera) {
        }
        @Override
        public void onOpened(SeekCamera sc) {
            seekCamera = sc;
            seekCamera.createSeekCameraCaptureSession(seekImageReader);
        }
        @Override
        public void onStarted(SeekCamera seekCamera) {
        }
        @Override
        public void onStopped(SeekCamera seekCamera) {
        }
        @Override
        public void onClosed(SeekCamera seekCamera) {
        }
        @Override
        public void onMemoryAccess(SeekCamera camera, SeekCamera.MemoryRegion region, int progress){
            SeekLogger.debug("Main Activity", "SeekCamera Memory Progress: " + progress);
        }
        @Override
        public void onError(SeekCamera seekCamera, Exception e) {
        }
    };
    @Override
    protected void onCreate(Bundle savedInstanceState) {
        super.onCreate(savedInstanceState);
        setContentView(R.layout.activity_main);
        thermographyInfo = findViewById(R.id.thermography_info);
        seekImageReader = new SeekImageReader();
        seekImageReader.setOnImageAvailableListener(this);
        seekCameraManager = new SeekCameraManager(this, null, stateCallback);
    }
    @Override
    public void onImageAvailable(final SeekImage seekImage) {
        runOnUiThread(() -> {
            String text = seekCamera.toString() + "\nMin: " +
                seekImage.getThermography().getMinTemp().toString() + "\n" +
                "Spot: " + seekImage.getThermography().getSpotTemp().toString() + "\n" +
                "Max: " + seekImage.getThermography().getMaxTemp().toString();
            thermographyInfo.setText(text);
        });
    }
}

```

## Application Screenshot

Here is a screenshot of the completed application:



**Figure 3.4 Screenshot**



## Chapter 4

# Seek Upgrade Example


This example shows you how to create an application to upgrade the firmware on a Seek Thermal Camera with Android Studio and the Seek Thermal Android SDK.

1. Create the Android Studio project
2. Change the AndroidManifest.xml file
3. Add Seek Android SDK to project
4. Create the User Interface
5. Write the MainActivity.java code
6. Application Screenshot

### Create the Android Studio project

To create your new Android project, follow these steps:


1. In the Welcome to Android Studio window, click Start a new Android Studio project or if you have a project already opened, select File > New > New Project.
2. In the Choose your project window, select Empty Activity and click Next.



**Figure 4.1 New Project**

3. In the Configure your project window, complete the following:





**Figure 4.2 Configure Project**

- Enter "Seek Upgrade" in the Name field.
- Enter "com.example.seekupgrade" in the Package name field.
- If you'd like to place the project in a different folder, change its Save location.
- Select Java from the Language drop-down menu.
- Select the checkbox next to Use androidx.\* artifacts.
- Click Finish.

## Change the AndroidManifest.xml file

Insert the following USB Device Intents to the AndroidManifest.xml file for ".MainActivity":

```
<activity android:name=".MainActivity">
  <intent-filter>
    <action android:name="android.intent.action.MAIN" />
    <category android:name="android.intent.category.LAUNCHER" />
    <action android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED" />
  </intent-filter>
  <meta-data android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED"
    android:resource="@xml/seekware_device_filter" />
</activity>
```

## Add Seek Android SDK to project

The Seek Thermal Android SDK is delivered as an AAR (Android Archive) for use with Android Studio and Gradle.

1. Open up the project structure by right-clicking on your project and choosing "Open Module Settings" or choosing "File" > "Project Structure..."
2. Click the "+" button in the top left to add a new module.
3. Choose "Import .JAR or .AAR Package" and click the "Next" button.
4. Find your file using the ellipsis button ("...") beside the "File name" field. Studio will automatically create a subproject name. Click "Finish".
5. Gradle will sync, which may take a few minutes. Add the new module as a dependency to your app. In the "Project Structure..." window, a new module has appeared representing the SDK. Keep the app's module selected and click on the Dependencies pane.
6. Use the "+" button at the bottom of the dependencies screen, and choose "module dependency". The dependencies screen is quite tall, so this button might be invisible at first.
7. The screen that pops up should show the Seekware\_Android\_4.0. Click "OK".

## Create the User Interface for the Application:

Overwrite the res/layout/activity\_main.xml file:




Figure 4.3 User Interface

```
<?xml version="1.0" encoding="utf-8"?>
<androidx.constraintlayout.widget.ConstraintLayout
    xmlns:android="http://schemas.android.com/apk/res/android"
    xmlns:app="http://schemas.android.com/apk/res-auto"
    xmlns:tools="http://schemas.android.com/tools"
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    tools:context=".MainActivity">
    <ListView
        android:id="@+id/list_view"
        android:layout_width="match_parent"
        android:layout_height="wrap_content"
        app:layout_constraintTop_toTopOf="parent"
        app:layout_constraintLeft_toLeftOf="parent"
        app:layout_constraintRight_toRightOf="parent"
    />
    <TextView
        android:id="@+id/camera_info"
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:text="@string/no_camera_found"
        app:layout_constraintBottom_toTopOf="@id/progress_bar"
        app:layout_constraintLeft_toLeftOf="parent"
        app:layout_constraintRight_toRightOf="parent"
    />
    <ProgressBar
        android:id="@+id/progress_bar"

```

```

        style="@android:style/Widget.ProgressBar.Horizontal"
        android:layout_width="match_parent"
        android:layout_height="wrap_content"
        android:progress="0"
        android:max="100"
        android:progressTint="@color/colorPrimary"
        app:layout_constraintBottom_toTopOf="@id/upgrade"
        app:layout_constraintLeft_toLeftOf="parent"
        app:layout_constraintRight_toRightOf="parent"
    />
<Button
    android:id="@+id/upgrade"
    android:layout_width="match_parent"
    android:layout_height="wrap_content"
    android:text="@string/upgrade"
    android:backgroundTint="@color/colorPrimary"
    android:textColor="#ffffff"
    app:layout_constraintBottom_toBottomOf="parent"
    app:layout_constraintLeft_toLeftOf="parent"
    app:layout_constraintRight_toRightOf="parent"
    android:onClick="onUpgradeClicked"/>
</androidx.constraintlayout.widget.ConstraintLayout>

```

## Write the MainActivity.java code

Add the following handlers to the MainActivity.java source file:

```

package com.example.seekupgrade;
import androidx.appcompat.app.AppCompatActivity;
import android.os.Bundle;
import android.os.Handler;
import android.os.HandlerThread;
import android.view.View;
import android.widget.AdapterView;
import android.widget.Button;
import android.widget.ListView;
import android.widget.ProgressBar;
import android.widget.TextView;
import android.widget.Toast;
import com.thermal.seekware.SeekCamera;
import com.thermal.seekware.SeekCameraManager;
import com.thermal.seekware.SeekUtility;
import java.util.List;
public class MainActivity extends AppCompatActivity {
    private HandlerThread handlerThread;
    private Handler handler;
    private ListView listView;
    private ProgressBar progressBar;
    private Button upgradeButton;
    private TextView cameraInfo;
    private String selectedFirmwareFile = null;
    private SeekCameraManager seekCameraManager;
    private SeekCamera seekCamera;
    private SeekCamera.StateCallback stateCallback = new SeekCamera.StateCallback() {
        @Override
        public void onInitialized(SeekCamera camera) {
        }
        @Override
        public void onOpened(SeekCamera camera) {
            seekCamera = camera;
            runOnUiThread(() -> {
                cameraInfo.setText(seekCamera.toString());
                if(selectedFirmwareFile != null){
                    upgradeButton.setVisibility(View.VISIBLE);
                }
            });
        }
        @Override
        public void onStarted(SeekCamera camera) {
        }
        @Override
        public void onStopped(SeekCamera camera) {
        }
        @Override
        public void onClosed(SeekCamera camera) {
            runOnUiThread(() -> cameraInfo.setText(getString(R.string.no_camera_found)));
        }
        @Override
        public void onMemoryAccess(SeekCamera camera, SeekCamera.MemoryRegion region, final int progress) {
            runOnUiThread(() -> progressBar.setProgress(progress));
        }
        @Override
    }
}

```


```

    public void onReboot(SeekCamera seekCamera) {
        Toast.makeText(getApplicationContext(), getString(R.string.reboot), Toast.LENGTH_SHORT).show();
        runOnUiThread(() -> cameraInfo.setText(getString(R.string.reboot)));
    }
    @Override
    public void onError(SeekCamera camera, Exception e) {
        Toast.makeText(getApplicationContext(), "Firmware upgrade failed!", Toast.LENGTH_SHORT).show();
    }
};
@Override
protected void onCreate(Bundle savedInstanceState) {
    super.onCreate(savedInstanceState);
    setContentView(R.layout.activity_main);
    listView = findViewById(R.id.list_view);
    List<String> listFirmware = SeekUtility.findFirmwareUpgradeFiles(this, "32K");
    ArrayAdapter listAdapter = new ArrayAdapter(this, android.R.layout.simple_list_item_1,
listFirmware);
    listView.setAdapter(listAdapter);
    listView.setOnItemClickListener((adapterView, view, i, l) -> {
        selectedFirmwareFile = adapterView.getAdapter().getItem(i).toString();
        upgradeButton.setText("UPGRADE to " + selectedFirmwareFile);
        upgradeButton.setVisibility(View.VISIBLE);
    });
    progressBar = findViewById(R.id.progress_bar);
    progressBar.setVisibility(View.INVISIBLE);
    cameraInfo = findViewById(R.id.camera_info);
    upgradeButton = findViewById(R.id.upgrade);
    upgradeButton.setVisibility(View.INVISIBLE);
    handlerThread = new HandlerThread("Background");
    handlerThread.start();
    handler = new Handler(handlerThread.getLooper());
    seekCameraManager = new SeekCameraManager(this, handler, stateCallback);
}
public void onUpgradeClicked(View v){
    if(seekCamera != null && selectedFirmwareFile != null){
        progressBar.setVisibility(View.VISIBLE);
        seekCamera.upgradeFirmware(selectedFirmwareFile, true);
    }
}
}

```

## Application Screenshot

Here is a screenshot of the completed application:



**Figure 4.4 Screenshot**

## Chapter 5


# Seek Simple Example

This example shows you how to create a Simple Thermal Camera application with Android Studio and the Seek Thermal Android SDK.

1. Create the Android Studio project
2. Change the AndroidManifest.xml file
3. Add Seek Android SDK to project
4. Create the User Interface
5. Write the MainActivity.java code
6. Application Screenshot

### Create the Android Studio project

To create your new Android project, follow these steps:

1. In the Welcome to Android Studio window, click Start a new Android Studio project or if you have a project already opened, select File > New > New Project.
2. In the Choose your project window, select Empty Activity and click Next.  

3. In the Configure your project window, complete the following:
  - Enter "Seek Simple" in the Name field.
  - Enter "com.example.seeksimple" in the Package name field.
  - If you'd like to place the project in a different folder, change its Save location.
  - Select Java from the Language drop-down menu.
  - Select the checkbox next to Use androidx.\* artifacts.
  - Click Finish.




Figure 5.1 Configure Project

## Change the AndroidManifest.xml file

Insert the following USB Device Intents to the AndroidManifest.xml file for ".MainActivity":

```
<activity android:name=".MainActivity">
    <intent-filter>
        <action android:name="android.intent.action.MAIN" />
        <category android:name="android.intent.category.LAUNCHER" />
        <action android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED" />
    </intent-filter>
    <meta-data android:name="android.hardware.usb.action.USB_DEVICE_ATTACHED"
        android:resource="@xml/seekware_device_filter" />
</activity>
```

## Add Seek Android SDK to project

The Seekware Android 4.0 SDK is delivered as an AAR (Android Archive) for use with Android Studio and Gradle.

1. Open up the project structure by right-clicking on your project and choosing "Open Module Settings" or choosing "File" > "Project Structure..."



- ## Create the User Interface for the Application

1. Create the res/drawable/arrow.xml resource:

2. Create the `res/drawable/camera.xml` resource:

3. Create the `res/drawable/ic_info.xml` resource:

#### 4. Create the res/drawable/square.xml resource

5. Overwrite the `res/values/strings.xml` resource:

Generated by Doxygen

```

    <string name="ff">FF</string>
    <string name="prev_pal">"- Pal"</string>
    <string name="next_pal">"Pal +"</string>
    <string name="settings">Settings</string>
</resources>

```

6. Create the Portrait User Interface layout:




Figure 5.2 Portrait User Interface

by overwriting the `res/layout/main_activity.xml` file:

```

<?xml version="1.0" encoding="utf-8"?>
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:id="@+id/main_activity"
    android:layout_width="fill_parent"
    android:layout_height="fill_parent"
    android:orientation="vertical">
    <LinearLayout
        android:layout_width="match_parent"
        android:layout_height="50sp"
        android:background="#ff000000"
        android:gravity="center|top"
        android:orientation="horizontal">
        <Space

```

```

        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
<Button
    android:id="@+id/btn_logo"
    android:layout_width="40sp"
    android:layout_height="40sp"
    android:background="@mipmap/ic_launcher"
    android:contentDescription="@string/logo"
    android:visibility="visible"
    android:onClick="clickLogo" />
<Space
    android:layout_width="wrap_content"
    android:layout_height="wrap_content"
    android:layout_weight="1" />
<Button
    android:id="@+id/btn_flatfield"
    android:textColor="#ffffffff"
    android:layout_width="40sp"
    android:layout_height="40sp"
    android:background="@drawable/square"
    android:contentDescription="@string/flatfield"
    android:onClick="clickFlatField" />
<Space
    android:layout_width="wrap_content"
    android:layout_height="wrap_content"
    android:layout_weight="1" />
<Button
    android:id="@+id/btn_info"
    android:layout_width="40sp"
    android:layout_height="40sp"
    android:background="@drawable/ic_info"
    android:contentDescription="@string/info"
    android:onClick="clickInfo" />
<Space
    android:layout_width="wrap_content"
    android:layout_height="wrap_content"
    android:layout_weight="1" />
</LinearLayout>
<com.thermal.seekware.SeekImageView
    android:id="@+id/seek_preview"
    android:layout_width="match_parent"
    android:layout_height="0dp"
    android:layout_weight="15" />
<LinearLayout
    android:layout_width="match_parent"
    android:layout_height="50sp"
    android:background="#ff000000"
    android:gravity="bottom|center"
    android:orientation="horizontal">
    <Space
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
    <Button
        android:id="@+id/btn_prev_pal"
        android:layout_width="40sp"
        android:layout_height="40sp"
        android:background="@drawable/arrow"
        android:contentDescription="@string/prev_pal"
        android:onClick="clickPrevPalette" />
    <Space
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
    <Button
        android:id="@+id/btn_capture"
        android:layout_width="40sp"
        android:layout_height="40sp"
        android:background="@drawable/camera"
        android:contentDescription="@string/capture"
        android:onClick="clickCapture" />
    <Space
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
    <Button
        android:id="@+id/btn_next_pal"
        android:layout_width="40sp"
        android:layout_height="40sp"
        android:background="@drawable/arrow"
        android:rotation="180"
        android:contentDescription="@string/next_pal"
        android:onClick="clickNextPalette" />
    <Space
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"

```

```
        android:layout_weight="1" />
    </LinearLayout>
</LinearLayout>
```

1. Create the Landscape User Interface layout:




Figure 5.3 Landscape User Interface

by creating the `res/layout-land/main_activity.xml` in a text editor:

```

<?xml version="1.0" encoding="utf-8"?>
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"
    xmlns:tools="http://schemas.android.com/tools"
    android:id="@+id/main_activity"
    android:layout_width="fill_parent"
    android:layout_height="fill_parent"
    android:orientation="horizontal">
    <LinearLayout
        android:layout_width="50sp"
        android:layout_height="match_parent"
        android:background="#ff000000"
        android:layout_weight="1"
        android:gravity="center|start"
        android:orientation="vertical">
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
        <Button
            android:id="@+id/btn_info"
            android:layout_width="40sp"
            android:layout_height="40sp"
            android:background="@drawable/ic_info"
            android:contentDescription="@string/info"
            android:onClick="clickInfo"
            android:visibility="visible" />
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
        <Button
            android:id="@+id/btn_flatfield"
            android:textColor="#ffffffff"
            android:layout_width="40sp"
            android:layout_height="40sp"
            android:background="@drawable/square"
            android:contentDescription="@string/flatfield"
            android:onClick="clickFlatField"
            android:visibility="visible" />
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
        <Button
            android:id="@+id/btn_logo"
            android:layout_width="40sp"
            android:layout_height="40sp"
            android:background="@mipmap/ic_launcher"
            android:contentDescription="@string/logo"
            android:visibility="visible"
            android:onClick="clickLogo" />
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
    </LinearLayout>
    <com.thermal.seekware.SeekImageView
        android:id="@+id/seek_preview"
        android:layout_width="match_parent"
        android:layout_height="match_parent"
        android:layout_weight="15" />
    <LinearLayout
        android:layout_width="50sp"
        android:layout_height="match_parent"
        android:layout_weight="1"
        android:background="#ff000000"
        android:gravity="end|center"
        android:orientation="vertical">
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
        <Button
            android:id="@+id/btn_next_pal"
            android:layout_width="40sp"
            android:layout_height="40sp"
            android:background="@drawable/arrow"
            android:rotation="90"
            android:contentDescription="@string/next_pal"
            android:onClick="clickNextPalette"
            android:visibility="visible" />
        <Space
            android:layout_width="match_parent"
            android:layout_height="wrap_content"
            android:layout_weight="1" />
        <Button
            android:id="@+id/btn_capture"

```

```

        android:layout_width="40sp"
        android:layout_height="40sp"
        android:background="@drawable/camera"
        android:contentDescription="@string/capture"
        android:onClick="clickCapture"
        android:visibility="visible" />
    <Space
        android:layout_width="match_parent"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
    <Button
        android:id="@+id/btn_prev_pal"
        android:layout_width="40sp"
        android:layout_height="40sp"
        android:background="@drawable/arrow"
        android:rotation="270"
        android:contentDescription="@string/prev_pal"
        android:onClick="clickPrevPalette"
        android:visibility="visible" />
    <Space
        android:layout_width="match_parent"
        android:layout_height="wrap_content"
        android:layout_weight="1" />
</LinearLayout>
</LinearLayout>

```

## Write the MainActivity.java code

1. Create the MainActivity window. This version forces Full Screen mode and locks the screen orientation at startup in onCreate. It also overrides onFrameAvailable() and registers the callback to allow for capturing the (raw) Bitmap image.

```

package com.example.seeksimple;
import android.content.Intent;
import android.content.pm.ActivityInfo;
import androidx.annotation.NonNull;
import androidx.appcompat.app.AppCompatActivity;
import android.graphics.Bitmap;
import android.net.Uri;
import android.os.Bundle;
import android.os.Handler;
import android.view.View;
import android.view.Window;
import android.view.WindowManager;
import android.widget.Button;
import android.widget.Toast;
import com.thermal.seekware.SeekCamera;
import com.thermal.seekware.SeekCameraManager;
import com.thermal.seekware.SeekImage;
import com.thermal.seekware.SeekImageView;
import com.thermal.seekware.SeekUtility;
import java.io.File;
import java.io.FileOutputStream;
import java.io.IOException;
import java.text.SimpleDateFormat;
import java.util.Date;
import java.util.Locale;
import java.util.Objects;
import static android.os.Environment.getExternalStorageDirectory;
public class MainActivity extends AppCompatActivity implements SeekImageView.OnFrameAvailableListener
{
    /* Static Fields */
    private static final String TAG = MainActivity.class.getSimpleName();
    private Button flatFieldButton;
    private String captureFilename = null;
    private SeekCamera myCamera;
    private SeekCameraManager seekCameraManager;
    private SeekImageView seekPreview;
    private SeekCamera.StateCallback stateCallback = new SeekCamera.StateCallback() {
        @Override
        public void onInitialized(SeekCamera seekCamera) {
        }
        @Override
        public void onOpened(SeekCamera seekCamera) {
            myCamera = seekCamera;
            seekCamera.createSeekCameraCaptureSession(seekPreview);
        }
        @Override
        public void onStart(SeekCamera seekCamera) {
            // Set default Color LUT
            SetPalette(0);
        }
    }
}

```

```

        @Override
        public void onStoped(SeekCamera seekCamera) {
        }
        @Override
        public void onClosed(SeekCamera seekCamera) {
        }
        @Override
        public void onMemoryAccess(SeekCamera camera, SeekCamera.MemoryRegion region, final int
progress){
        }
        @Override
        public void onReboot(SeekCamera seekCamera) {
        }
        @Override
        public void onError(SeekCamera seekCamera, Exception e) {
        }

    };
    @Override
    public void onRequestPermissionsResult(int requestCode, @NonNull String[] permissions, @NonNull
int[] grantResults) {
    }
    @Override
    protected void onCreate(Bundle savedInstanceState) {
        //hide the title bar
        requestWindowFeature(Window.FEATURE_NO_TITLE);
        Objects.requireNonNull(getSupportActionBar()).hide();
        super.onCreate(savedInstanceState);
        //show the activity in full screen
        Window window = getWindow();
        window.setFlags(WindowManager.LayoutParams.FLAG_FULLSCREEN,
WindowManager.LayoutParams.FLAG_FULLSCREEN);
        // keep screen on
        window.addFlags(WindowManager.LayoutParams.FLAG_KEEP_SCREEN_ON);
        setContentView(R.layout.activity_main);
        setRequestedOrientation(ActivityInfo.SCREEN_ORIENTATION_LOCKED);
        flatFieldButton = findViewById(R.id.btn_flatfield);
        seekPreview = findViewById(R.id.seek_preview);
        seekPreview.setOnFrameAvailableListener(this);
        seekCameraManager = new SeekCameraManager(this, null, stateCallback);
        SeekUtility.PermissionHandler.requestStoragePermission(this);
    }
}

```

## 2. Add the clickPrevPalette & clickNextPalette button handlers to MainActivity.java:

```

private int myPalette = 0;
final SeekCamera.ColorLut luts[] = {
    SeekCamera.ColorLut.TYRIAN,
    SeekCamera.ColorLut.IRON2,
    SeekCamera.ColorLut.RECON,
    SeekCamera.ColorLut.WHITEHOT,
    SeekCamera.ColorLut.BLACKHOT
};
// Change Camera Color LUT (index)
private void SetPalette(int lut) {
    myPalette = lut;
    if (myCamera != null) {
        myCamera.setColorLut(luts[lut]);
    }
}
public void clickPrevPalette(View v) {
    if (myPalette > 0) {
        SetPalette(myPalette - 1);
    } else {
        SetPalette(luts.length - 1);
    }
}
public void clickNextPalette(View v) {
    if (myPalette < luts.length - 1) {
        SetPalette(myPalette + 1);
    } else {
        SetPalette(0);
    }
}
}

```

## 3. Add the clickFlatField, clickInfo & clickLogo button handlers to MainActivity.java:

```

public void clickFlatField(View v) {
    if (myCamera != null) {
        Toast.makeText(this, "Flat Field", Toast.LENGTH_SHORT).show();
        myCamera.triggerShutter();
    }
}
public void clickInfo(View v) {
    if (myCamera != null) {
        String str = myCamera.toString();
        Toast.makeText(this, str, Toast.LENGTH_LONG).show();
    }
}
}

```

```

public void clickLogo(View v)
{
    String url = "http://www.thermal.com";
    Intent i = new Intent(Intent.ACTION_VIEW);
    i.setData(Uri.parse(url));
    startActivity(i);
}

```

#### 4. Add the clickCapture command handler and spot meter display code to the MainActivity.java:

```

String captureFilename = null;
void writeImageToPNG(String filename, Bitmap bmp) {
    File strFolder = getExternalStorageDirectory();
    String pathname = strFolder + "/Pictures/" + filename + ".png";
    FileOutputStream out = null;
    try {
        out = new FileOutputStream(pathname);
        bmp.compress(Bitmap.CompressFormat.PNG, 100, out); // bmp is your Bitmap instance
        // PNG is a lossless format, the compression factor (100) is ignored
    } catch (Exception e) {
        e.printStackTrace();
    } finally {
        try {
            if (out != null) {
                out.close();
            }
        } catch (IOException e) {
            e.printStackTrace();
        }
    }
}

public void clickCapture(View v) {
    if (seekPreview != null) {
        SimpleDateFormat formatter = new SimpleDateFormat("yyyyMMdd_HHmmss", Locale.US);
        Date now = new Date();
        captureFilename = "IR_" + formatter.format(now);
    }
}

// https://stackoverflow.com/questions/11140285/how-do-we-use-runOnUiThread-in-android
private void updateSpot(final float spotTemp)
{
    MainActivity.this.runOnUiThread(new Runnable() {
        public void run() {
            showSpot(spotTemp);
        }
    });
}

private void showSpot(final float spot)
{
    String spotStr = String.format("%.0f", spot);
    Button btnFlatField = (Button) this.findViewById(R.id.btn_flatfield);
    if (btnFlatField != null) {
        btnFlatField.setText(spotStr);
    }
}

@Override
public void onFrameAvailable(SeekImageView seekPreview, SeekImage seekImage) {
    SeekUtility.Temperature spotTemp = seekImage.getThermography().getSpotTemp();
    if (spotTemp != null) {
        updateSpot(spotTemp.getValue());
    }
    if (captureFilename != null) {
        // TODO: Add rotation to store image upright with USB Compact cameras on the bottom
        Toast.makeText(this, "Capture:" + captureFilename, Toast.LENGTH_SHORT).show();
        writeImageToPNG(captureFilename, seekImage.getColorBitmap());
        captureFilename = null;
    }
}
}

```

#### 5. Create the res/layout/firmware\_upgrade\_alert.xml resource in a text editor:

```

<?xml version="1.0" encoding="utf-8"?>
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    android:orientation="vertical">
    <ListView
        android:id="@+id/firmware_upgrade_bundle_list"
        android:layout_width="match_parent"
        android:layout_height="match_parent">
    </ListView>
    <ProgressBar
        android:id="@+id/firmware_upgrade_progress"
        style="@android:style/Widget.ProgressBar.Horizontal"
        android:layout_width="match_parent"
        android:layout_height="match_parent"
        android:progress="0"

```



```
        android:max="100"  
        android:progressTint="@color/colorPrimary">  
</ProgressBar>  
<TextView  
    android:id="@+id/firmware_upgrade_progress_text"  
    android:layout_width="match_parent"  
    android:layout_height="match_parent"  
    android:textAlignment="center">  
</TextView>  
</LinearLayout>
```

## Application Screenshot

Here is a screenshot of the completed application:




Figure 5.4 Screenshot



## Chapter 6

# Hierarchical Index

### 6.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

com.thermal.seekware.SeekCamera.AGCMode . . . . .	45
com.thermal.seekware.SeekCamera.AspectRatio . . . . .	46
com.thermal.seekware.SeekCamera.Characteristics . . . . .	52
com.thermal.seekware.SeekCamera.ColorLut . . . . .	57
com.thermal.seekware.SeekIOException.ErrorCode . . . . .	63
com.thermal.seekware.SeekPipelineException.ErrorCode . . . . .	64
com.thermal.seekware.SeekCamera.LensFacing . . . . .	66
com.thermal.seekware.SeekCamera.MemoryRegion . . . . .	67
com.thermal.seekware.Thermography.Metrics . . . . .	68
com.thermal.seekware.SeekImageView.OnFrameAvailableListener . . . . .	69
com.thermal.seekware.SeekImageReader.OnImageAvailableListener . . . . .	70
com.thermal.seekware.SeekCamera.Orientation . . . . .	71
com.thermal.seekware.SeekUtility.OrientationManager . . . . .	73
com.thermal.seekware.SeekUtility.PermissionHandler.Permission . . . . .	74
com.thermal.seekware.SeekUtility.PermissionHandler . . . . .	74
com.thermal.seekware.SeekCamera . . . . .	75
com.thermal.seekware.SeekCameraManager . . . . .	87
com.thermal.seekware.SeekCamera.SeekExceptionListener . . . . .	89
com.thermal.seekware.SeekImage . . . . .	90
com.thermal.seekware.SeekIOException . . . . .	96
com.thermal.seekware.SeekLogger . . . . .	96
com.thermal.seekware.SeekPipelineException . . . . .	101
com.thermal.seekware.SeekPipelineListener . . . . .	102
com.thermal.seekware.SeekImageReader . . . . .	91
com.thermal.seekware.SeekImageView . . . . .	93
com.thermal.seekware.SeekPipeline . . . . .	100
com.thermal.seekware.SeekUtility . . . . .	103
com.thermal.seekware.SeekCamera.State . . . . .	111
com.thermal.seekware.SeekUtility.PermissionHandler.StateCallback . . . . .	113
com.thermal.seekware.SeekCamera.StateCallback . . . . .	113
com.thermal.seekware.SeekUtility.Temperature . . . . .	116
com.thermal.seekware.Thermography . . . . .	118
com.thermal.seekware.SeekUtility.Temperature.Unit . . . . .	125



## Chapter 7

# Class Index

### 7.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">com.thermal.seekware.SeekCamera.AGCMode</a>	
Automatic gain control (AGC) mode	45
<a href="#">com.thermal.seekware.SeekCamera.AspectRatio</a>	
Controls the stretching of the image	46
<a href="#">com.thermal.seekware.SeekCamera.Characteristics</a>	
Holds information about the <a href="#">SeekCamera</a>	52
<a href="#">com.thermal.seekware.SeekCamera.ColorLut</a>	
Color Look Up Table (LUT)	57
<a href="#">com.thermal.seekware.SeekIOException.ErrorCode</a>	
Error codes that describe communication failures between the SDK and a <a href="#">SeekCamera</a>	63
<a href="#">com.thermal.seekware.SeekPipelineException.ErrorCode</a>	
Custom error codes	64
<a href="#">com.thermal.seekware.SeekCamera.LensFacing</a>	
Direction the camera lens is facing	66
<a href="#">com.thermal.seekware.SeekCamera.MemoryRegion</a>	
Specifies the region of firmware memory to read or write	67
<a href="#">com.thermal.seekware.Thermography.Metrics</a>	
Simple struct to hold average, min, and max temperatures	68
<a href="#">com.thermal.seekware.SeekImageView.OnFrameAvailableListener</a>	
Listens for an available frame	69
<a href="#">com.thermal.seekware.SeekImageReader.OnImageAvailableListener</a>	
Called when a <a href="#">SeekImage</a> is available	70
<a href="#">com.thermal.seekware.SeekCamera.Orientation</a>	
Orientation used for image rendering	71
<a href="#">com.thermal.seekware.SeekUtility.OrientationManager</a>	
Manages orientation of the devices and rotation of views and overlays	73
<a href="#">com.thermal.seekware.SeekUtility.PermissionHandler.Permission</a>	
Represents a permission request	74
<a href="#">com.thermal.seekware.SeekUtility.PermissionHandler</a>	
Handles Android 6+ permissions	74
<a href="#">com.thermal.seekware.SeekCamera</a>	
The main control for the pipeline	75
<a href="#">com.thermal.seekware.SeekCameraManager</a>	
Manages <a href="#">SeekCamera</a> creation	87
<a href="#">com.thermal.seekware.SeekCamera.SeekExceptionListener</a>	
Listens for SeekIOExceptions	89

<a href="#">com.thermal.seekware.SeekImage</a>	
The object sent through the imaging pipeline . . . . .	90
<a href="#">com.thermal.seekware.SeekImageReader</a>	
Provides imaging and thermography from the camera directly to the user . . . . .	91
<a href="#">com.thermal.seekware.SeekImageView</a>	
Draws a thermal image to the screen . . . . .	93
<a href="#">com.thermal.seekware.SeekIOException</a>	
IOException with custom error codes . . . . .	96
<a href="#">com.thermal.seekware.SeekLogger</a>	
Controls and filters logging . . . . .	96
<a href="#">com.thermal.seekware.SeekPipeline</a>	
Extend this class to do your own processing on a <a href="#">SeekCamera</a> by overriding process() . . . . .	100
<a href="#">com.thermal.seekware.SeekPipelineException</a>	
Runtime exception with custom error codes . . . . .	101
<a href="#">com.thermal.seekware.SeekPipelineListener</a>	
Allows for callbacks between <a href="#">SeekPipeline</a> objects when a <a href="#">SeekImage</a> is ready for processing . . . . .	102
<a href="#">com.thermal.seekware.SeekUtility</a>	
Contains utility classes, functions, for use with this SDK . . . . .	103
<a href="#">com.thermal.seekware.SeekCamera.State</a>	
The current state of the camera . . . . .	111
<a href="#">com.thermal.seekware.SeekUtility.PermissionHandler.StateCallback</a>	
Callback for when a permission is granted . . . . .	113
<a href="#">com.thermal.seekware.SeekCamera.StateCallback</a>	
Allows for callbacks to the states of the camera . . . . .	113
<a href="#">com.thermal.seekware.SeekUtility.Temperature</a>	
Represents an immutable temperature with a value and a unit . . . . .	116
<a href="#">com.thermal.seekware.Thermography</a>	
Holds thermography data from a <a href="#">SeekCamera</a> . . . . .	118
<a href="#">com.thermal.seekware.SeekUtility.Temperature.Unit</a>	
Represents a temperature unit (C, F or K) . . . . .	125

## Chapter 8

# Class Documentation

### 8.1 com.thermal.seekware.SeekCamera.AGCMode Enum Reference

Automatic gain control (AGC) mode.

#### Public Attributes

- [LEGACY\\_HISTEQ](#)
- [LINEAR](#)
- [HISTEQ](#)

#### 8.1.1 Detailed Description

Automatic gain control (AGC) mode.

The automatic gain control (AGC) mode used by the camera

#### 8.1.2 Member Data Documentation

##### 8.1.2.1 HISTEQ

```
com.thermal.seekware.SeekCamera.AGCMode.HISTEQ
```

Default mode, uses histogram equalization Histogram Equalization

##### 8.1.2.2 LEGACY\_HISTEQ

```
com.thermal.seekware.SeekCamera.AGCMode.LEGACY_HISTEQ
```

Deprecated version of histogram equalization Legacy Histogram Equalization

### 8.1.2.3 LINEAR

```
com.thermal.seekware.SeekCamera.AGCMode.LINEAR
```

Linearly stretches the color bar to fit the range of temperatures Linear

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.2 com.thermal.seekware.SeekCamera.AspectRatio Enum Reference

Controls the stretching of the image.

### Public Attributes

- [MATCH\\_WIDTH](#)
- [MATCH\\_HEIGHT](#)
- [AUTO](#)

### 8.2.1 Detailed Description

Controls the stretching of the image.

The aspect ratio of the image will always be preserved (it will never be distorted). The actual aspect ratio of the display depends on the container that it is filling (to constrain a View to a specific ratio, you can use a [ConstraintLayout](#)). This describes how it fills the screen. In the images below, the areas within the green borders represents the screen, with the blue parts representing the image, and the black parts representing blank areas that result from the aspect ratio difference.

### 8.2.2 Member Data Documentation




### 8.2.2.1 AUTO

```
com.thermal.seekware.SeekCamera.AspectRatio.AUTO
```

This will act like MATCH\_WIDTH when the screen aspect ratio is less than the camera's, and MATCH\_HEIGHT when it is greater. There will never be any black bars in this mode, only portions of the image cut off. This is the default mode.



**Figure 8.1 Square Portrait**




**Figure 8.3 Square Landscape**


#### 8.2.2.2 MATCH\_HEIGHT

```
com.thermal.seekware.SeekCamera.AspectRatio.MATCH_HEIGHT
```

This will stretch the image to match the height of the screen. If the screen aspect ratio is greater than the camera's, the left and right will be cut off. If it less, then there will be black bars on the sides.



**Figure 8.5 Square Portrait**



**Figure 8.7 Square Landscape**

### 8.2.2.3 MATCH\_WIDTH

```
com.thermal.seekware.SeekCamera.AspectRatio.MATCH_WIDTH
```

This will stretch the image to match the width of the screen. If the screen aspect ratio is greater than the camera's, there will be black bars on the top and bottom. If it less, then the top and bottom will be cut off.



**Figure 8.9 Square Portrait**




Figure 8.11 Square Landscape

The documentation for this enum was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekCamera.java`

### 8.3 `com.thermal.seekware.SeekCamera.Characteristics` Class Reference

Holds information about the [SeekCamera](#).

#### Public Member Functions

- `int getWidth ()`
- `int getHeight ()`
- `SeekUtility.Temperature.Unit getTemperatureUnit ()`
- `void setTemperatureUnit (@NonNull SeekUtility.Temperature.Unit temperatureUnit)`
- `String getSerialNumber ()`
- `String getModelNumber ()`
- `String getFirmwareVersion ()`

- [LensFacing](#) `getLensFacing ()`
- void [setLensFacing](#) ([@NonNull LensFacing](#) lensFacing)
- [Orientation](#) `getOrientation ()`
- void [setOrientation](#) ([@NonNull Orientation](#) orientation)
- int [getCorrectedOrientation](#) ()
- int [getSensorOrientation](#) ()
- Point [convertScreenToSensorPoint](#) ([@NonNull Point](#) point, [@NonNull Size](#) screenSize)
- Point [convertSensorToScreenPoint](#) ([@NonNull Point](#) point, [@NonNull Size](#) screenSize)

### 8.3.1 Detailed Description

Holds information about the [SeekCamera](#).

Simple struct-like class that holds information associated with a [SeekCamera](#).

### 8.3.2 Member Function Documentation

#### 8.3.2.1 `convertScreenToSensorPoint()`

```
Point com.thermal.seekware.SeekCamera.Characteristics.convertScreenToSensorPoint (
    @NonNull Point point,
    @NonNull Size screenSize )
```

Rotate screen coordinates to sensor coordinates

##### Parameters

<i>point</i>	Point (X,Y) in screen coordinates to rotate
<i>screenSize</i>	width, height of screen

##### Returns

Point in FPA coordinates

#### 8.3.2.2 `convertSensorToScreenPoint()`

```
Point com.thermal.seekware.SeekCamera.Characteristics.convertSensorToScreenPoint (
    @NonNull Point point,
    @NonNull Size screenSize )
```

Rotate min/max coordinates to screen coordinates based on sensorOrientation

**Parameters**

<i>point</i>	Point (X,Y) in FPA coordinates to rotate
<i>screenSize</i>	width, height of screen

**Returns**

Point in logical sensor coordinates

**8.3.2.3 getCorrectedOrientation()**

```
int com.thermal.seekware.SeekCamera.Characteristics.getCorrectedOrientation ( )
```

Gets the corrected orientation based on orientation and sensor orientation

**Returns**

the corrected orientation

**8.3.2.4 getFirmwareVersion()**

```
String com.thermal.seekware.SeekCamera.Characteristics.getFirmwareVersion ( )
```

Gets the firmware version of this [SeekCamera](#). This is formatted as in the form 1.2.3.4, where

1. represents the major version number
2. represents the minor version number
3. represents the major build number
4. represents the minor build number

**Returns**

the firmware version

**8.3.2.5 getHeight()**

```
int com.thermal.seekware.SeekCamera.Characteristics.getHeight ( )
```

Gets the native sensor height of an image frame in pixels. This value is always less than [getWidth\(\)](#).

**Returns**

the native sensor height of an image frame



#### 8.3.2.6 getLensFacing()

[LensFacing](#) com.thermal.seekware.SeekCamera.Characteristics.getLensFacing ( )

Gets the current direction the lens is facing. Default is [LensFacing#BACK](#).

##### Returns

the current direction the lens is facing

#### 8.3.2.7 getModelNumber()

String com.thermal.seekware.SeekCamera.Characteristics.getModelNumber ( )

Gets the model number of this [SeekCamera](#)

##### Returns

the model number

#### 8.3.2.8 getOrientation()

[Orientation](#) com.thermal.seekware.SeekCamera.Characteristics.getOrientation ( )

Gets the current orientation. Default is [Orientation#ORIENTATION\\_0](#).

##### Returns

the orientation

#### 8.3.2.9 getSensorOrientation()

int com.thermal.seekware.SeekCamera.Characteristics.getSensorOrientation ( )

Gets the sensor orientation.

##### Returns

the orientation in degrees

#### 8.3.2.10 `getSerialNumber()`

```
String com.thermal.seekware.SeekCamera.Characteristics.getSerialNumber ( )
```

Gets the serial number of this [SeekCamera](#)

##### Returns

the serial number

#### 8.3.2.11 `getTemperatureUnit()`

```
SeekUtility.Temperature.Unit com.thermal.seekware.SeekCamera.Characteristics.getTemperature↔  
Unit ( )
```

Gets the current temperature units used by the camera. Default is Celsius.

##### Returns

the current temperature unit

#### 8.3.2.12 `getWidth()`

```
int com.thermal.seekware.SeekCamera.Characteristics.getWidth ( )
```

Gets the native sensor width of an image frame in pixels from the camera. This value is always more than [getHeight\(\)](#).

##### Returns

the native sensor width of an image frame

#### 8.3.2.13 `setLensFacing()`

```
void com.thermal.seekware.SeekCamera.Characteristics.setLensFacing (   
    @NonNull LensFacing lensFacing )
```

Sets the direction the lens is facing.

##### Parameters

<i>lensFacing</i>	the desired direction the lens is facing
-------------------	--

#### 8.3.2.14 setOrientation()

```
void com.thermal.seekware.SeekCamera.Characteristics.setOrientation (
    @NonNull Orientation orientation )
```

Sets the orientation to the given [Orientation](#)

##### Parameters

<i>orientation</i>	the desired orientation
--------------------	-------------------------

#### 8.3.2.15 setTemperatureUnit()

```
void com.thermal.seekware.SeekCamera.Characteristics.setTemperatureUnit (
    @NonNull SeekUtility.Temperature.Unit temperatureUnit )
```

Sets the temperature units used by the camera to the given unit.

##### Parameters

<i>temperatureUnit</i>	the desired temperature unit
------------------------	------------------------------

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.4 com.thermal.seekware.SeekCamera.ColorLut Enum Reference

Color Look Up Table (LUT)

### Static Public Member Functions

- static byte[] [createUserLut](#) (@ColorInt int startColor, @ColorInt int endColor)

### Public Attributes

- [WHITEHOT](#) =(100)
- [BLACKHOT](#) =(101)
- [SPECTRA](#) =(102)
- [PRISM](#) =(103)
- [TYRIAN](#) =(104)

- [IRON](#) =(105)
- [AMBER](#) =(106)
- [HI](#) =(107)
- [HILO](#) =(108)
- [IRON2](#) =(109)
- [GREEN](#) =(110)
- [RECON](#) =(111)
- [BLACK\\_RECON](#) =(112)
- [USER0](#) =(10000)
- [USER1](#) =(10001)
- [USER2](#) =(10002)
- [USER3](#) =(10003)
- [USER4](#) =(10004)

### 8.4.1 Detailed Description

Color Look Up Table (LUT)

Defines the list of color LUTs that can be applied to display video frames.

### 8.4.2 Member Function Documentation

#### 8.4.2.1 `createUserLut()`

```
static byte [ ] com.thermal.seekware.SeekCamera.ColorLut.createUserLut (
    @ColorInt int startColor,
    @ColorInt int endColor ) [static]
```

Creates a user lut with 256 colors that can be used with `loadUserLutData`

Parameters

<i>startColor</i>	the color at the beginning of the array
<i>endColor</i>	the color at the end of the array

Returns

a user lut with the gradient blended between the start and end color typically used with [SeekCamera.loadUserLutData](#)

### 8.4.3 Member Data Documentation

#### 8.4.3.1 AMBER

```
com.thermal.seekware.SeekCamera.ColorLut.AMBER =(106)
```

Amber LUT



#### 8.4.3.2 BLACK\_RECON

```
com.thermal.seekware.SeekCamera.ColorLut.BLACK_RECON =(112)
```

Black Recon LUT TODO: add images

#### 8.4.3.3 BLACKHOT

```
com.thermal.seekware.SeekCamera.ColorLut.BLACKHOT =(101)
```

Black Hot LUT



#### 8.4.3.4 GREEN

```
com.thermal.seekware.SeekCamera.ColorLut.GREEN =(110)
```

Green LUT



#### 8.4.3.5 HI

```
com.thermal.seekware.SeekCamera.ColorLut.HI =(107)
```

Hi LUT



#### 8.4.3.6 HILO

```
com.thermal.seekware.SeekCamera.ColorLut.HILO =(108)
```

HiLo LUT



#### 8.4.3.7 IRON

```
com.thermal.seekware.SeekCamera.ColorLut.IRON =(105)
```

Iron LUT



#### 8.4.3.8 IRON2

```
com.thermal.seekware.SeekCamera.ColorLut.IRON2 =(109)
```

Iron2 LUT



#### 8.4.3.9 PRISM

```
com.thermal.seekware.SeekCamera.ColorLut.PRISM =(103)
```

Prism LUT



#### 8.4.3.10 RECON

```
com.thermal.seekware.SeekCamera.ColorLut.RECON =(111)
```

Recon LUT



#### 8.4.3.11 SPECTRA

```
com.thermal.seekware.SeekCamera.ColorLut.SPECTRA =(102)
```

Spectra LUT



#### 8.4.3.12 TYRIAN

```
com.thermal.seekware.SeekCamera.ColorLut.TYRIAN =(104)
```

Tyrian LUT



#### 8.4.3.13 USER0

```
com.thermal.seekware.SeekCamera.ColorLut.USER0 =(10000)
```

User LUT #0

See also

Must be loaded first using [loadUserLutData](#)

#### 8.4.3.14 USER1

```
com.thermal.seekware.SeekCamera.ColorLut.USER1 =(10001)
```

User LUT #1

See also

Must be loaded first using [loadUserLutData](#)

#### 8.4.3.15 USER2

```
com.thermal.seekware.SeekCamera.ColorLut.USER2 =(10002)
```

User LUT #2

See also

Must be loaded first using [loadUserLutData](#)

#### 8.4.3.16 USER3

```
com.thermal.seekware.SeekCamera.ColorLut.USER3 =(10003)
```

User LUT #3

See also

Must be loaded first using [loadUserLutData](#)



#### 8.4.3.17 USER4

```
com.thermal.seekware.SeekCamera.ColorLut.USER4 =(10004)
```

User LUT #4

See also

Must be loaded first using [loadUserLutData](#)

#### 8.4.3.18 WHITEHOT

```
com.thermal.seekware.SeekCamera.ColorLut.WHITEHOT =(100)
```

White Hot LUT



The documentation for this enum was generated from the following file:

- [seekware/src/main/java/com/thermal/seekware/SeekCamera.java](#)

## 8.5 com.thermal.seekware.SeekIOException.ErrorCode Enum Reference

Error codes that describe communication failures between the SDK and a [SeekCamera](#).

### Public Member Functions

- int [value](#) ()

### Static Public Member Functions

- static boolean [contains](#) (int value)
- static [ErrorCode](#) [get](#) (int value)

#### 8.5.1 Detailed Description

Error codes that describe communication failures between the SDK and a [SeekCamera](#).

This enum contains error codes associated with IO errors in the SDK

#### 8.5.2 Member Function Documentation

##### 8.5.2.1 contains()

```
static boolean com.thermal.seekware.SeekIOException.ErrorCode.contains (
    int value ) [static]
```

Returns true if the given value is in the enum

**Parameters**

<i>value</i>	the desired value
--------------	-------------------

**Returns**

whether or not the value is in the enum

**8.5.2.2 get()**

```
static ErrorCode com.thermal.seekware.SeekIOException.ErrorCode.get (
    int value ) [static]
```

Gets the code for the given value and returns it

**Parameters**

<i>value</i>	the desired value
--------------	-------------------

**Returns**

the code for the given value

**8.5.2.3 value()**

```
int com.thermal.seekware.SeekIOException.ErrorCode.value ( )
```

Getter for this.value

**Returns**

the error code of this enum

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekIOException.java

## 8.6 com.thermal.seekware.SeekPipelineException.ErrorCode Enum Reference

Custom error codes.

## Public Member Functions

- int [value](#) ()

## Static Public Member Functions

- static boolean [contains](#) (int value)
- static [ErrorCode](#) [get](#) (int value)

### 8.6.1 Detailed Description

Custom error codes.

This enum contains error codes associated with all types of errors in the SDK

### 8.6.2 Member Function Documentation

#### 8.6.2.1 contains()

```
static boolean com.thermal.seekware.SeekPipelineException.ErrorCode.contains (  
    int value ) [static]
```

Returns true if the given value is in the enum

##### Parameters

<i>value</i>	the desired value
--------------	-------------------

##### Returns

whether or not the value is in the enum

#### 8.6.2.2 get()

```
static ErrorCode com.thermal.seekware.SeekPipelineException.ErrorCode.get (  
    int value ) [static]
```

Gets the code for the given value and returns it

##### Parameters

<i>value</i>	the desired value
--------------	-------------------

**Returns**

the code for the given value

**8.6.2.3 value()**

```
int com.thermal.seekware.SeekPipelineException.ErrorCode.value ( )
```

Getter for this.value

**Returns**

the error code of this enum

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekPipelineException.java

## 8.7 com.thermal.seekware.SeekCamera.LensFacing Enum Reference

Direction the camera lens is facing.

**Public Attributes**

- [FRONT](#)
- [BACK](#)

### 8.7.1 Detailed Description

Direction the camera lens is facing.

Which direction the camera lens is facing

### 8.7.2 Member Data Documentation

#### 8.7.2.1 BACK

```
com.thermal.seekware.SeekCamera.LensFacing.BACK
```

traditional back facing camera Back facing

### 8.7.2.2 FRONT

```
com.thermal.seekware.SeekCamera.LensFacing.FRONT
```

selfie camera, flips only the preview horizontally, the media capture will be in the sensor orientation Front facing (selfie)

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.8 com.thermal.seekware.SeekCamera.MemoryRegion Enum Reference

Specifies the region of firmware memory to read or write.

### Public Attributes

- [NEW\\_IMAGE](#)
- [IMAGE0](#)
- [IMAGE1](#)

### 8.8.1 Detailed Description

Specifies the region of firmware memory to read or write.

### 8.8.2 Member Data Documentation

#### 8.8.2.1 IMAGE0

```
com.thermal.seekware.SeekCamera.MemoryRegion.IMAGE0
```

The region of firmware memory used to store the first firmware image.

#### 8.8.2.2 IMAGE1

```
com.thermal.seekware.SeekCamera.MemoryRegion.IMAGE1
```

The region of firmware memory used to store the second firmware image.

### 8.8.2.3 NEW\_IMAGE

```
com.thermal.seekware.SeekCamera.MemoryRegion.NEW_IMAGE
```

The region of firmware memory used to store a new firmware image.

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.9 com.thermal.seekware.Thermography.Metrics Class Reference

Simple struct to hold average, min, and max temperatures.

### Public Member Functions

- SeekUtility.Temperature [getAverage](#) ()
- SeekUtility.Temperature [getMin](#) ()
- SeekUtility.Temperature [getMax](#) ()

### 8.9.1 Detailed Description

Simple struct to hold average, min, and max temperatures.

### 8.9.2 Member Function Documentation

#### 8.9.2.1 getAverage()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.Metrics.getAverage ( )
```

Gets the average temperature

#### Returns

the average temperature

### 8.9.2.2 getMax()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.Metrics.getMax ( )
```

Gets the max temperature

#### Returns

the max temperature

### 8.9.2.3 getMin()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.Metrics.getMin ( )
```

Gets the min temperature

#### Returns

the min temperature

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/Thermography.java

## 8.10 com.thermal.seekware.SeekImageView.OnFrameAvailableListener Interface Reference

Listens for an available frame.

### Public Member Functions

- void [onFrameAvailable](#) ([SeekImageView](#) seekImageView, [SeekImage](#) seekImage)

### 8.10.1 Detailed Description

Listens for an available frame.

### 8.10.2 Member Function Documentation

#### 8.10.2.1 onFrameAvailable()

```
void com.thermal.seekware.SeekImageView.OnFrameAvailableListener.onFrameAvailable (
    SeekImageView seekImageView,
    SeekImage seekImage )
```

Called when a frame is available

## Parameters

<i>seekImageView</i>	<a href="#">SeekImageView</a> associated with callback
<i>seekImage</i>	<a href="#">SeekImage</a> associated with callback

The documentation for this interface was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekImageView.java`

## 8.11 com.thermal.seekware.SeekImageReader.OnImageAvailableListener Interface Reference

Called when a [SeekImage](#) is available.

### Public Member Functions

- void [onImageAvailable](#) ([SeekImage](#) seekImage)

#### 8.11.1 Detailed Description

Called when a [SeekImage](#) is available.

Listens for when a [SeekImage](#) is available

#### 8.11.2 Member Function Documentation

##### 8.11.2.1 onImageAvailable()

```
void com.thermal.seekware.SeekImageReader.OnImageAvailableListener.onImageAvailable (
    SeekImage seekImage )
```

Called once the pipeline is fully completed one cycle and has an image ready for use

## Parameters

<i>seekImage</i>	the <a href="#">SeekImage</a> associated with the callback
------------------	--

The documentation for this interface was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekImageReader.java`



## 8.12 com.thermal.seekware.SeekCamera.Orientation Enum Reference

[Orientation](#) used for image rendering.

### Public Member Functions

- [int getCorrectedOrientation](#) (int sensorOrientation)
- [Orientation next](#) ()
- [Orientation previous](#) ()

### Public Attributes

- [ORIENTATION\\_0](#) =(0)
- [ORIENTATION\\_90](#) =(90)
- [ORIENTATION\\_180](#) =(180)
- [ORIENTATION\\_270](#) =(270)

### 8.12.1 Detailed Description

[Orientation](#) used for image rendering.

Refers to the orientation in which to render the image

### 8.12.2 Member Function Documentation

#### 8.12.2.1 getCorrectedOrientation()

```
int com.thermal.seekware.SeekCamera.Orientation.getCorrectedOrientation (
    int sensorOrientation )
```

Gets the corrected orientation (adjusted for SPI and USB native sensor orientation). Note: this value will always be clamped between 0 and 360.

#### Parameters

<i>sensorOrientation</i>	the sensor orientation from SeekCameraConnection
--------------------------	--

#### Returns

the corrected orientation in degrees (between 0 and 360)

### 8.12.2.2 next()

`Orientation` `com.thermal.seekware.SeekCamera.Orientation.next ( )`

Gets the next `Orientation`

#### Returns

the next `Orientation` in the sequence

### 8.12.2.3 previous()

`Orientation` `com.thermal.seekware.SeekCamera.Orientation.previous ( )`

Gets the previous `Orientation`

#### Returns

the previous `Orientation` in the sequence

## 8.12.3 Member Data Documentation

### 8.12.3.1 ORIENTATION\_0

`com.thermal.seekware.SeekCamera.Orientation.ORIENTATION_0 =(0)`

`Orientation` 0 Degrees

### 8.12.3.2 ORIENTATION\_180

`com.thermal.seekware.SeekCamera.Orientation.ORIENTATION_180 =(180)`

`Orientation` 180 Degrees

### 8.12.3.3 ORIENTATION\_270

`com.thermal.seekware.SeekCamera.Orientation.ORIENTATION_270 =(270)`

`Orientation` 270 Degrees

#### 8.12.3.4 ORIENTATION\_90

```
com.thermal.seekware.SeekCamera.Orientation.ORIENTATION_90 =(90)
```

[Orientation](#) 90 Degrees

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.13 com.thermal.seekware.SeekUtility.OrientationManager Class Reference

Manages orientation of the devices and rotation of views and overlays.

Inherits LifecycleObserver.

### Public Member Functions

- int [getOrientation](#) ()
- int [getRawOrientation](#) ()
- void [addViews](#) (View... views)

#### 8.13.1 Detailed Description

Manages orientation of the devices and rotation of views and overlays.

This class handles the orientation as well as rotating views that should be rotated with the screen orientation.

#### 8.13.2 Member Function Documentation

##### 8.13.2.1 addViews()

```
void com.thermal.seekware.SeekUtility.OrientationManager.addViews (  
    View...  views )
```

Adds any numbers of views that should be rotated with the screen orientation

### 8.13.2.2 `getOrientation()`

```
int com.thermal.seekware.SeekUtility.OrientationManager.getOrientation ( )
```

Gets the orientation for saving images and returns it

#### Returns

the orientation in degrees

### 8.13.2.3 `getRawOrientation()`

```
int com.thermal.seekware.SeekUtility.OrientationManager.getRawOrientation ( )
```

Gets the raw orientation and returns it

#### Returns

the raw orientation in degrees

The documentation for this class was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekUtility.java`

## 8.14 `com.thermal.seekware.SeekUtility.PermissionHandler.Permission` Enum Reference

Represents a permission request.

### 8.14.1 Detailed Description

Represents a permission request.

The documentation for this enum was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekUtility.java`

## 8.15 `com.thermal.seekware.SeekUtility.PermissionHandler` Class Reference

Handles Android 6+ permissions.

## Classes

- enum [Permission](#)  
*Represents a permission request.*
- interface [StateCallback](#)  
*Callback for when a permission is granted.*

### 8.15.1 Detailed Description

Handles Android 6+ permissions.

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekUtility.java

## 8.16 com.thermal.seekware.SeekCamera Class Reference

The main control for the pipeline.

Inherits LifecycleObserver.

## Classes

- enum [AGCMode](#)  
*Automatic gain control (AGC) mode.*
- enum [AspectRatio](#)  
*Controls the stretching of the image.*
- class [Characteristics](#)  
*Holds information about the [SeekCamera](#).*
- enum [ColorLut](#)  
*Color Look Up Table (LUT)*
- enum [LensFacing](#)  
*Direction the camera lens is facing.*
- enum [MemoryRegion](#)  
*Specifies the region of firmware memory to read or write.*
- enum [Orientation](#)  
*[Orientation](#) used for image rendering.*
- interface [SeekExceptionListener](#)  
*Listens for SeekIOExceptions.*
- enum [State](#)  
*The current state of the camera.*
- interface [StateCallback](#)  
*Allows for callbacks to the states of the camera.*

## Public Member Functions

- [AspectRatio](#) [getAspectRatio](#) ()
- void [setAspectRatio](#) (@NonNull [AspectRatio](#) aspectRatio)
- float [getEmissivity](#) ()
- void [setEmissivity](#) (float emissivity)
- boolean [getImageSmoothing](#) ()
- void [setImageSmoothing](#) (boolean imageSmoothing)
- [ColorLut](#) [getColorLut](#) ()
- void [setColorLut](#) (@NonNull [ColorLut](#) colorLut)
- String [getColorLutName](#) ()
- void [setSeekExceptionListener](#) ([SeekExceptionListener](#) seekExceptionListener)
- [Characteristics](#) [getCharacteristics](#) ()
- ByteBuffer [getColorPalette](#) ()
- ByteBuffer [getColorPalette](#) ([ColorLut](#) colorLut)
- [State](#) [getCurrentState](#) ()
- String [getChipId](#) ()
- void [triggerShutter](#) ()
- void [suspendShutter](#) ()
- void [resumeShutter](#) ()
- void [loadUserLutData](#) (byte[] userLutData, [ColorLut](#) userLut)
- void [setAGCMode](#) (@NonNull [AGCMode](#) agcMode)
- synchronized void [open](#) ()
- synchronized void [start](#) ()
- synchronized void [stop](#) ()
- synchronized void [close](#) ()
- synchronized void [memoryRead](#) ([MemoryRegion](#) region, byte[] data) throws [UnsupportedOperationException](#)
- synchronized void [memoryRead](#) ([MemoryRegion](#) region, int regionOffset, byte[] data) throws [UnsupportedOperationException](#)
- synchronized void [memoryWrite](#) ([MemoryRegion](#) region, int regionOffset, byte[] data)
- synchronized void [memoryWrite](#) ([MemoryRegion](#) region, byte[] data)
- void [upgradeFirmware](#) (String firmwareFilename, boolean rebootAfterUpgrade)
- void [upgradeFirmware](#) (String firmwareFilename, boolean rebootAfterUpgrade, int rebootMsDelay)
- synchronized void [reboot](#) (int msDelay)
- void [createSeekCameraCaptureSession](#) (boolean getFiltered, boolean getTherm, boolean getColor, [SeekPipelineListener](#)... listeners)
- void [createSeekCameraCaptureSession](#) ([SeekPipelineListener](#)... listeners)
- String [toString](#) ()

### 8.16.1 Detailed Description

The main control for the pipeline.

## Overview

Controls and accesses features of image processing, contains information about the state and properties of the camera, manages receiving raw frames from USB or SPI and sending them through image processing and then delivering them to the pipeline.

## Lifecycle




Figure 8.13 SeekCamera Lifecycle

The lifecycle management of a [SeekCamera](#) is handled automatically. The [StateCallback](#) allows for interfacing with different states of the camera:

- [open\(\)](#) is called when the camera is created
- [start\(\)](#) is called when the SeekCameraCaptureSession is created (and the application starts)
- [stop\(\)](#) is called when the application stops
- [close\(\)](#) is called when the camera is detached

### 8.16.2 Member Function Documentation

**8.16.2.1 close()**

```
synchronized void com.thermal.seekware.SeekCamera.close ( )
```

Closes the [SeekCamera](#). Puts the camera to sleep (if supported) and frees all resources used by the camera and the imaging pipeline.

**8.16.2.2 createSeekCameraCaptureSession() [1/2]**

```
void com.thermal.seekware.SeekCamera.createSeekCameraCaptureSession (
    boolean getFiltered,
    boolean getTherm,
    boolean getColor,
    SeekPipelineListener... listeners )
```

Creates a SeekCameraCaptureSession with the given parameters and starts the camera

**Parameters**

<i>getFiltered</i>	whether or not to request a 16bit, pre-AGC filtered image from the camera.
<i>getTherm</i>	whether or not to get the thermography image from the camera.
<i>getColor</i>	whether or not to get the color image from the camera.
<i>listeners</i>	the listeners to attach to the SeekCameraCaptureSession

**8.16.2.3 createSeekCameraCaptureSession() [2/2]**

```
void com.thermal.seekware.SeekCamera.createSeekCameraCaptureSession (
    SeekPipelineListener... listeners )
```

Creates a SeekCameraCaptureSession with the given parameters and starts the camera

**Parameters**

<i>listeners</i>	the listeners to attach to the SeekCameraCaptureSession
------------------	---

**8.16.2.4 getAspectRatio()**

```
AspectRatio com.thermal.seekware.SeekCamera.getAspectRatio ( )
```

Gets the aspect ratio

**Returns**

the aspect ratio to display the image in



### 8.16.2.5 getCharacteristics()

`Characteristics` com.thermal.seekware.SeekCamera.getCharacteristics ( )

Gets the current characteristics

#### Returns

the characteristics associated with this [SeekCamera](#)

### 8.16.2.6 getChipId()

`String` com.thermal.seekware.SeekCamera.getChipId ( )

Gets the ChipId of the camera

#### Returns

String containing Chip ID from Sensor

### 8.16.2.7 getColorLut()

`ColorLut` com.thermal.seekware.SeekCamera.getColorLut ( )

Gets the current color lut used by the camera.

#### Returns

the color lut

### 8.16.2.8 getColorLutName()

`String` com.thermal.seekware.SeekCamera.getColorLutName ( )

Gets the current color lut used by the cameras name as a string

#### Returns

The current color lut's name as a String

#### 8.16.2.9 getColorPalette() [1/2]

```
ByteBuffer com.thermal.seekware.SeekCamera.getColorPalette ( )
```

Gets a ByteBuffer of the current color LUT palette

##### Returns

a ByteBuffer with 256 colors representing the current color lut

#### 8.16.2.10 getColorPalette() [2/2]

```
ByteBuffer com.thermal.seekware.SeekCamera.getColorPalette (
    ColorLut colorLut )
```

Gets a ByteBuffer of the desired color LUT palette

##### Returns

a ByteBuffer with 256 colors representing the given color lut

#### 8.16.2.11 getCurrentState()

```
State com.thermal.seekware.SeekCamera.getCurrentState ( )
```

Gets the current camera state

##### Returns

the state the camera is currently in

#### 8.16.2.12 getEmissivity()

```
float com.thermal.seekware.SeekCamera.getEmissivity ( )
```

Gets the current emissivity of the camera.

##### Returns

The emissivity

**8.16.2.13 getImageSmoothing()**

```
boolean com.thermal.seekware.SeekCamera.getImageSmoothing ( )
```

Gets the current image smoothing setting of the camera.

**Returns**

The image smoothing

**8.16.2.14 loadUserLutData()**

```
void com.thermal.seekware.SeekCamera.loadUserLutData (
    byte[] userLutData,
    ColorLut userLut )
```

Loads lut data into the given user lut

**Parameters**

<i>userLutData</i>	byte array that contains the user color lut
<i>userLut</i>	the desired lut to set the data for

**See also**

userLutData can be created for gradient ramps using [ColorLut.createUserLut](#)

**8.16.2.15 memoryRead() [1/2]**

```
synchronized void com.thermal.seekware.SeekCamera.memoryRead (
    MemoryRegion region,
    byte[] data ) throws UnsupportedOperationException
```

Reads data from the [SeekCamera](#)'s internal memory at the specified region. NOTE: The function is a synchronous, blocking call and will only return when either the memory access has completed successfully or an error has occurred. The caller of this function is responsible to calling this function on a background thread, if desired.

**Parameters**

<i>region</i>	The memory region of the <a href="#">SeekCamera</a> 's internal memory to read from.
<i>data</i>	A buffer to store the data read from the <a href="#">SeekCamera</a> .

**Exceptions**

<i>UnsupportedOperationException</i>	if reading from the specified region is not supported by the camera.
--------------------------------------	--

## Exceptions

<a href="#">SeekIOException</a>	if communication with the <a href="#">SeekCamera</a> fails.
<a href="#">IllegalStateException</a>	if the <a href="#">SeekCamera</a> is Closed or Started. The internal memory of a <a href="#">SeekCamera</a> can only be accessed in the Stopped state.

8.16.2.16 `memoryRead()` [2/2]

```
synchronized void com.thermal.seekware.SeekCamera.memoryRead (
    MemoryRegion region,
    int regionOffset,
    byte[] data ) throws UnsupportedOperationException
```

Reads data from the [SeekCamera](#)'s internal memory at the specified region and offset. NOTE: The function is a synchronous, blocking call and will only return when either the memory access has completed successfully or an error has occurred. The caller of this function is responsible to calling this function on a background thread, if desired.

## Parameters

<i>region</i>	The memory region of the <a href="#">SeekCamera</a> 's internal memory to read from.
<i>regionOffset</i>	Offset (in bytes) into the memory region to begin reading from.
<i>data</i>	A buffer to store the data read from the <a href="#">SeekCamera</a> .

## Exceptions

<a href="#">UnsupportedOperationException</a>	if reading from the specified region is not supported by the current camera.
<a href="#">SeekIOException</a>	if communication with the <a href="#">SeekCamera</a> fails
<a href="#">IllegalStateException</a>	if the <a href="#">SeekCamera</a> is Closed or Started. The internal memory of a <a href="#">SeekCamera</a> can only be accessed in the Stopped state.

8.16.2.17 `memoryWrite()` [1/2]

```
synchronized void com.thermal.seekware.SeekCamera.memoryWrite (
    MemoryRegion region,
    byte[] data )
```

Writes data to the [SeekCamera](#)'s internal memory at the specified region. NOTE: The function is a synchronous, blocking call and will only return when either the memory access has completed successfully or an error has occurred. The caller of this function is responsible to calling this function on a background thread, if desired.

## Parameters

<i>region</i>	The memory region of the <a href="#">SeekCamera</a> 's internal memory to write to.
<i>data</i>	The data to write to the <a href="#">SeekCamera</a> 's internal memory.

## Exceptions

<a href="#"><i>SeekIOException</i></a>	if communication with the <a href="#">SeekCamera</a> fails or the camera firmware does not support writing to the specified region
<i>IllegalStateException</i>	if the <a href="#">SeekCamera</a> is Closed or Started. The internal memory of a <a href="#">SeekCamera</a> can only be accessed in the Stopped state.

8.16.2.18 `memoryWrite()` [2/2]

```
synchronized void com.thermal.seekware.SeekCamera.memoryWrite (
    MemoryRegion region,
    int regionOffset,
    byte[] data )
```

Writes data to the [SeekCamera](#)'s internal memory at the specified region and offset. NOTE: The function is a synchronous, blocking call and will only return when either the memory access has completed successfully or an error has occurred. The caller of this function is responsible to calling this function on a background thread, if desired.

## Parameters

<i>region</i>	The memory region of the <a href="#">SeekCamera</a> 's internal memory to write to.
<i>regionOffset</i>	Offset (in bytes) into the memory region to begin writing to.
<i>data</i>	The data to write to the <a href="#">SeekCamera</a> 's internal memory.

## Exceptions

<a href="#"><i>SeekIOException</i></a>	if communication with the <a href="#">SeekCamera</a> fails or the camera firmware does not support writing to the specified region
<i>IllegalStateException</i>	if the <a href="#">SeekCamera</a> is Closed or Started. The internal memory of a <a href="#">SeekCamera</a> can only be accessed in the Stopped state.

8.16.2.19 `open()`

```
synchronized void com.thermal.seekware.SeekCamera.open ( )
```

Opens a [SeekCamera](#) and prepares it to be run.

## Exceptions

<i>InstantiationException</i>	if the camera cannot be initialized
<a href="#"><i>SeekIOException</i></a>	if there is a problem communicating with the camera
<i>IllegalStateException</i>	if this <a href="#">SeekCamera</a> is already open

### 8.16.2.20 reboot()

```
synchronized void com.thermal.seekware.SeekCamera.reboot (
    int msDelay )
```

Reboots a [SeekCamera](#) after the specified delay.

#### Parameters

<i>msDelay</i>	milliseconds to wait before rebooting the camera.
----------------	---

### 8.16.2.21 resumeShutter()

```
void com.thermal.seekware.SeekCamera.resumeShutter ( )
```

Resumes the shutter (USB cameras only)

### 8.16.2.22 setAGCMode()

```
void com.thermal.seekware.SeekCamera.setAGCMode (
    @NonNull AGCMode agcMode )
```

Sets the camera's AGC mode

#### Parameters

<i>agcMode</i>	the desired AGC mode
----------------	----------------------

### 8.16.2.23 setAspectRatio()

```
void com.thermal.seekware.SeekCamera.setAspectRatio (
    @NonNull AspectRatio aspectRatio )
```

Sets the aspect ratio to the given value

#### Parameters

<i>aspectRatio</i>	the desired aspect ratio
--------------------	--------------------------

### 8.16.2.24 setColorLut()

```
void com.thermal.seekware.SeekCamera.setColorLut (
    @NonNull ColorLut colorLut )
```

Sets the current color lut used by the camera.

#### Parameters

<i>colorLut</i>	the desired color lut
-----------------	-----------------------

### 8.16.2.25 setEmissivity()

```
void com.thermal.seekware.SeekCamera.setEmissivity (
    float emissivity )
```

Sets the current emissivity of the camera.

#### Parameters

<i>emissivity</i>	the desired emissivity
-------------------	------------------------

### 8.16.2.26 setImageSmoothing()

```
void com.thermal.seekware.SeekCamera.setImageSmoothing (
    boolean imageSmoothing )
```

Sets the image smoothing setting of the camera.

#### Parameters

<i>imageSmoothing</i>	the desired image smoothing
-----------------------	-----------------------------

### 8.16.2.27 setSeekExceptionListener()

```
void com.thermal.seekware.SeekCamera.setSeekExceptionListener (
    SeekExceptionListener seekExceptionListener )
```

Sets the [SeekExceptionListener](#) to the given parameter

## Parameters

<i>seekExceptionListener</i>	the desired <a href="#">SeekExceptionListener</a>
------------------------------	---

**8.16.2.28 start()**

```
synchronized void com.thermal.seekware.SeekCamera.start ( )
```

Starts the camera. Prepares the event driven imaging pipeline, wakes up the camera (if it is asleep), and begins processing image frames from the camera.

## Exceptions

<i>IllegalStateException</i>	if this <a href="#">SeekCamera</a> is not open
------------------------------	--

**8.16.2.29 stop()**

```
synchronized void com.thermal.seekware.SeekCamera.stop ( )
```

Stops the camera. Puts the cameras to sleep (if supported) and shuts down the imaging pipeline.

## Exceptions

<i>IllegalStateException</i>	if this <a href="#">SeekCamera</a> is not open
------------------------------	--

**8.16.2.30 suspendShutter()**

```
void com.thermal.seekware.SeekCamera.suspendShutter ( )
```

Suspends the shutter (USB cameras only)

**8.16.2.31 toString()**

```
String com.thermal.seekware.SeekCamera.toString ( )
```

Override default [toString\(\)](#) method

## Returns

a string with the model number, firmware version, and camera version



**8.16.2.32 triggerShutter()**

```
void com.thermal.seekware.SeekCamera.triggerShutter ( )
```

Triggers a shutter for a USB camera, or a flat field for a SPI camera

**8.16.2.33 upgradeFirmware() [1/2]**

```
void com.thermal.seekware.SeekCamera.upgradeFirmware (
    String firmwareFilename,
    boolean rebootAfterUpgrade )
```

Upgrades the firmware on this [SeekCamera](#), then reboots the camera after 150ms, if requested

**Parameters**

<i>firmwareFilename</i>	the firmware file to upgrade with, found in assets
<i>rebootAfterUpgrade</i>	whether or not to reboot the camera after the upgrade is completed

**8.16.2.34 upgradeFirmware() [2/2]**

```
void com.thermal.seekware.SeekCamera.upgradeFirmware (
    String firmwareFilename,
    boolean rebootAfterUpgrade,
    int rebootMsDelay )
```

Upgrades the firmware on this [SeekCamera](#), then reboots the camera after the given delay, if requested

**Parameters**

<i>firmwareFilename</i>	the firmware file to upgrade with, found in assets
<i>rebootAfterUpgrade</i>	whether or not to reboot the camera after the upgrade is completed
<i>rebootMsDelay</i>	the delay to wait in milliseconds for rebooting the camera (ignored if <i>rebootAfterUpgrade</i> is false)

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

**8.17 com.thermal.seekware.SeekCameraManager Class Reference**

Manages [SeekCamera](#) creation.

Inherits LifecycleObserver.

## Public Member Functions

- [SeekCameraManager](#) (Context [context](#), Handler *handler*, SeekCamera.StateCallback listener)
- int [getUSBDeviceCount](#) ()

## Protected Attributes

- Context [context](#)

### 8.17.1 Detailed Description

Manages [SeekCamera](#) creation.

This class manages the SeekCameraReceiver that creates a [SeekCamera](#) when it is attached. Simply instantiate this class and it will automatically handle connecting to SPI and USB SeekCameras. Note: it is important that you store a reference to this object when created, even if there are no calls to it, as it will get garbage collected if you instantiate it in a local scope like onCreate.

The implementation of this class varies greatly from the camera2 android.hardware.camera2.CameraManager, as the USB cameras are not always connected, so it makes more sense to create them automatically in response to certain events (USB device attached, application start up (with a device already attached)).

### 8.17.2 Constructor & Destructor Documentation

#### 8.17.2.1 SeekCameraManager()

```
com.thermal.seekware.SeekCameraManager.SeekCameraManager (
    Context context,
    Handler handler,
    SeekCamera.StateCallback listener )
```

Initializer Constructor

#### Parameters

<i>context</i>	application context
<i>handler</i>	application handler
<i>listener</i>	the listener to attach to the <a href="#">SeekCamera</a> when it is created

### 8.17.3 Member Function Documentation

### 8.17.3.1 getUSBDeviceCount()

```
int com.thermal.seekware.SeekCameraManager.getUSBDeviceCount ( )
```

Gets the number of USB devices currently connected

#### Returns

the number of USB devices currently connected

## 8.17.4 Member Data Documentation

### 8.17.4.1 context

```
Context com.thermal.seekware.SeekCameraManager.context [protected]
```

Application context, passed from the constructor

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCameraManager.java

## 8.18 com.thermal.seekware.SeekCamera.SeekExceptionListener Interface Reference

Listens for SeekIOExceptions.

### Public Member Functions

- void [onSeekIOException](#) ([SeekCamera](#) camera, [SeekIOException](#) seekIOException)

### 8.18.1 Detailed Description

Listens for SeekIOExceptions.

## 8.18.2 Member Function Documentation

### 8.18.2.1 onSeekIOException()

```
void com.thermal.seekware.SeekCamera.SeekExceptionListener.onSeekIOException (
    SeekCamera camera,
    SeekIOException seekIOException )
```

Called when a [SeekIOException](#) occurs, on the same thread that the error occurred on

**Parameters**

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
<i>seekIOException</i>	the <a href="#">SeekIOException</a> generated

The documentation for this interface was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekCamera.java

## 8.19 com.thermal.seekware.SeekImage Class Reference

The object sent through the imaging pipeline.

### Public Member Functions

- ByteBuffer [getFilteredBuffer](#) ()
- [Thermography](#) [getThermography](#) ()
- Bitmap [getColorBitmap](#) ()
- int [getColorsUsed](#) ()

#### 8.19.1 Detailed Description

The object sent through the imaging pipeline.

This class is what is sent through the imaging pipeline, originating from a [SeekCameraCaptureSession](#) and going through as many [SeekPipelines](#) as specified and then to an output such as [SeekImageView](#). It contains all information related to the thermal image.

#### 8.19.2 Member Function Documentation

##### 8.19.2.1 [getColorBitmap](#)()

```
Bitmap com.thermal.seekware.SeekImage.getColorBitmap ( )
```

Gets the color bitmap and returns it

#### Returns

the color bitmap of this image

**8.19.2.2 getColorsUsed()**

```
int com.thermal.seekware.SeekImage.getColorsUsed ( )
```

Gets the number of colors used for the color bar and returns it

**Returns**

the number of colors used for the color bar (0-256)

**8.19.2.3 getFilteredBuffer()**

```
ByteBuffer com.thermal.seekware.SeekImage.getFilteredBuffer ( )
```

Gets the filtered buffer and returns it Note: this is formatted like a flat byte array, so use SeekUtility.flatten to convert a 2D Point into a flat index.

**Returns**

the filtered buffer associated with this image

**8.19.2.4 getThermography()**

```
Thermography com.thermal.seekware.SeekImage.getThermography ( )
```

Gets the thermography and returns it. Note: The thermography will only be valid for this image only. If you plan on using values from this class for longer than one frame time, you must make a copy or there will be a chance that the data will be overridden.

**Returns**

the thermography associated with this image


The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekImage.java

**8.20 com.thermal.seekware.SeekImageReader Class Reference**

Provides imaging and thermography from the camera directly to the user.

Inheritance diagram for com.thermal.seekware.SeekImageReader:



## Classes

- interface [OnImageAvailableListener](#)  
*Called when a [SeekImage](#) is available.*

## Public Member Functions

- [SeekImageReader](#) ()
- [SeekImageReader](#) ([SeekPipeline](#) input)
- void [setOnImageAvailableListener](#) ([OnImageAvailableListener](#) onImageAvailableListener)
- void [onImageSent](#) ([SeekImage](#) image)

### 8.20.1 Detailed Description

Provides imaging and thermography from the camera directly to the user.

This class's primary function is to provide direct access to thermal data to the end user. NOTE: You must specifically request for the filtered buffer in `SeekCameraCaptureSession` or else the filtered buffer in the [SeekImage](#) provided by the callback will be null.

### 8.20.2 Constructor & Destructor Documentation

#### 8.20.2.1 [SeekImageReader](#)() [1/2]

```
com.thermal.seekware.SeekImageReader.SeekImageReader ( )
```

Default Constructor

#### 8.20.2.2 [SeekImageReader](#)() [2/2]

```
com.thermal.seekware.SeekImageReader.SeekImageReader (
    SeekPipeline input )
```

Pipeline Constructor

Parameters

<i>input</i>	where to listen for input
--------------	---------------------------

### 8.20.3 Member Function Documentation

### 8.20.3.1 onImageSent()

```
void com.thermal.seekware.SeekImageReader.onImageSent (
    SeekImage image )
```

Callback for seekPipeline.sendImage()

#### Parameters

<i>image</i>	the <a href="#">SeekImage</a> associated with the callback
--------------	--

Implements [com.thermal.seekware.SeekPipelineListener](#).

### 8.20.3.2 setOnImageAvailableListener()

```
void com.thermal.seekware.SeekImageReader.setOnImageAvailableListener (
    OnImageAvailableListener onImageAvailableListener )
```

Sets the [OnImageAvailableListener](#)

#### Parameters

<i>onImageAvailableListener</i>	the desired listener for this class
---------------------------------	-------------------------------------


The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekImageReader.java

## 8.21 com.thermal.seekware.SeekImageView Class Reference

Draws a thermal image to the screen.

Inheritance diagram for com.thermal.seekware.SeekImageView:



### Classes

- interface [OnFrameAvailableListener](#)  
*Listens for an available frame.*

## Public Member Functions

- [SeekImageView](#) (Context context, [SeekPipeline](#) input)
- [SeekImageView](#) (Context context)
- [SeekImageView](#) (Context context, AttributeSet attrs)
- void [setInput](#) ([SeekPipeline](#) input)
- void [onImageSent](#) ([SeekImage](#) image)
- void [setOnFrameAvailableListener](#) ([OnFrameAvailableListener](#) onFrameAvailableListener)

### 8.21.1 Detailed Description

Draws a thermal image to the screen.

This class processes SeekImages from either a SeekCameraCaptureSession or a [SeekPipeline](#) and renders them into a GLSurfaceView.

### 8.21.2 Constructor & Destructor Documentation

#### 8.21.2.1 SeekImageView() [1/3]

```
com.thermal.seekware.SeekImageView.SeekImageView (
    Context context,
    SeekPipeline input )
```

[SeekPipeline](#) Constructor

Parameters

<i>context</i>	application context
<i>input</i>	imaging pipeline object to render

#### 8.21.2.2 SeekImageView() [2/3]

```
com.thermal.seekware.SeekImageView.SeekImageView (
    Context context )
```

SeekCameraCaptureSession Constructor

Parameters

<i>context</i>	application context
----------------	---------------------



### 8.21.2.3 SeekImageView() [3/3]

```
com.thermal.seekware.SeekImageView.SeekImageView (
    Context context,
    AttributeSet attrs )
```

Default View Constructor Called when a view is added to an xml layout.

#### Parameters

<i>context</i>	application context
<i>attrs</i>	attribute set

## 8.21.3 Member Function Documentation

### 8.21.3.1 onImageSent()

```
void com.thermal.seekware.SeekImageView.onImageSent (
    SeekImage image )
```

Callback for seekPipeline.sendImage()

#### Parameters

<i>image</i>	the <a href="#">SeekImage</a> associated with the callback
--------------	--

Implements [com.thermal.seekware.SeekPipelineListener](#).

### 8.21.3.2 setInput()

```
void com.thermal.seekware.SeekImageView.setInput (
    SeekPipeline input )
```

Updates the rendering input for this View

#### Parameters

<i>input</i>	imaging pipeline object to receive data from
--------------	--

### 8.21.3.3 setOnFrameAvailableListener()

```
void com.thermal.seekware.SeekImageView.setOnFrameAvailableListener (
    OnFrameAvailableListener onFrameAvailableListener )
```

Sets the [OnFrameAvailableListener](#) to the given parameter

Parameters

<i>onFrameAvailableListener</i>	the desired listener
---------------------------------	----------------------

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekImageView.java

## 8.22 com.thermal.seekware.SeekIOException Class Reference

IOException with custom error codes.

Inherits IOException.

### Classes

- enum [ErrorCode](#)  
*Error codes that describe communication failures between the SDK and a [SeekCamera](#).*

### 8.22.1 Detailed Description

IOException with custom error codes.

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekIOException.java

## 8.23 com.thermal.seekware.SeekLogger Class Reference

Controls and filters logging.

### Static Public Member Functions

- static void [setFilter](#) (int filter)
- static void [addTagFilters](#) (String... tags)
- static void [verbose](#) (String tag, String msg)
- static void [debug](#) (String tag, String msg)
- static void [info](#) (String tag, String msg)
- static void [warn](#) (String tag, String msg)
- static void [error](#) (String tag, String msg)

## Static Public Attributes

- static final int [ALL](#) = 0x11111
- static final int [NONE](#) = 0x00000

### 8.23.1 Detailed Description

Controls and filters logging.

This class is a wrapper around the Android Log that allows for filtering by channel as well as filtering by tag.

### 8.23.2 Member Function Documentation

#### 8.23.2.1 addTagFilters()

```
static void com.thermal.seekware.SeekLogger.addTagFilters (
    String... tags ) [static]
```

Adds a filter that only logs the messages that match the desired tags.

##### Parameters

<i>tags</i>	tags that should be logged
-------------	----------------------------

#### 8.23.2.2 debug()

```
static void com.thermal.seekware.SeekLogger.debug (
    String tag,
    String msg ) [static]
```

Logs to the debug channel if the filters allow

##### Parameters

<i>tag</i>	class tag
<i>msg</i>	message to log

#### 8.23.2.3 error()

```
static void com.thermal.seekware.SeekLogger.error (
```

```
String tag,  
String msg ) [static]
```

Logs to the error channel if the filters allow

#### Parameters

<i>tag</i>	class tag
<i>msg</i>	message to log

#### 8.23.2.4 info()

```
static void com.thermal.seekware.SeekLogger.info (  
    String tag,  
    String msg ) [static]
```

Logs to the info channel if the filters allow

#### Parameters

<i>tag</i>	class tag
<i>msg</i>	message to log

#### 8.23.2.5 setFilter()

```
static void com.thermal.seekware.SeekLogger.setFilter (  
    int filter ) [static]
```

Sets the filter for logging specific channels (debug, info, warning, error, verbose). To filter for only certain channels, you can bitwise or the constants in [SeekLogger](#) to get only the specified channels. For example, if you only want debug and info logs, you would change the following line to: [SeekLogger.setFilter](#)(SeekLogger.DEBUG | SeekLogger.INFO);

#### Parameters

<i>filter</i>	the filter to apply to all logging
---------------	------------------------------------

#### 8.23.2.6 verbose()

```
static void com.thermal.seekware.SeekLogger.verbose (  
    String tag,  
    String msg ) [static]
```

Logs to the verbose channel if the filters allow

## Parameters

<i>tag</i>	class tag
<i>msg</i>	message to log

**8.23.2.7 warn()**

```
static void com.thermal.seekware.SeekLogger.warn (  
    String tag,  
    String msg ) [static]
```

Logs to the warning channel if the filters allow

## Parameters

<i>tag</i>	class tag
<i>msg</i>	message to log

**8.23.3 Member Data Documentation****8.23.3.1 ALL**

```
final int com.thermal.seekware.SeekLogger.ALL = 0x11111 [static]
```

Turns on all logging

**8.23.3.2 NONE**

```
final int com.thermal.seekware.SeekLogger.NONE = 0x00000 [static]
```

Turns off all logging


The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekLogger.java

## 8.24 com.thermal.seekware.SeekPipeline Class Reference

Extend this class to do your own processing on a [SeekCamera](#) by overriding process().

Inheritance diagram for com.thermal.seekware.SeekPipeline:



### Public Member Functions

- void [onImageSent](#) ([SeekImage](#) image)

### Protected Attributes

- [SeekPipeline](#) input
- [SeekImage](#) image

#### 8.24.1 Detailed Description

Extend this class to do your own processing on a [SeekCamera](#) by overriding process().

This abstract class is the building block for processing SeekImages in the SDK imaging pipeline. If you would like to design and insert your own processing steps that operate on the thermal or imaging data from a [SeekCamera](#), you can extend this class and insert your own processing steps.

NOTE: Any processing steps you design must be less than 1 frame time. Timing Requirements on process(): < 8fps: 120ms < 9fps: 110ms < 16fps: 60ms < 18fps: 50ms < 27fps: 35ms

For compatibility with all [SeekCamera](#)'s we recommend no more that 30ms of processing.

#### 8.24.2 Member Function Documentation

##### 8.24.2.1 onImageSent()

```
void com.thermal.seekware.SeekPipeline.onImageSent (  
    SeekImage image )
```

Callback for seekPipeline.sendImage()

## Parameters

<i>image</i>	the <a href="#">SeekImage</a> associated with the callback
--------------	--

Implements [com.thermal.seekware.SeekPipelineListener](#).

## 8.24.3 Member Data Documentation

### 8.24.3.1 image

[SeekImage](#) `com.thermal.seekware.SeekPipeline.image` [protected]

The [SeekImage](#) that will be sent after this has finished processing

### 8.24.3.2 input

[SeekPipeline](#) `com.thermal.seekware.SeekPipeline.input` [protected]

Where the input should be received from. If this is null, this [SeekPipeline](#) should be directly attached to a [SeekCameraCaptureSession](#)

The documentation for this class was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekPipeline.java`

## 8.25 com.thermal.seekware.SeekPipelineException Class Reference

Runtime exception with custom error codes.

Inherits [RuntimeException](#).

### Classes

- enum [ErrorCode](#)  
*Custom error codes.*

### Public Member Functions

- [ErrorCode](#) `getErrorCode ()`

### 8.25.1 Detailed Description

Runtime exception with custom error codes.

### 8.25.2 Member Function Documentation

#### 8.25.2.1 `getErrorCode()`

```
ErrorCode com.thermal.seekware.SeekPipelineException.getErrorCode ( )
```

Gets the error code associated with this exception

Returns

the error code associated with this exception


The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekPipelineException.java

## 8.26 com.thermal.seekware.SeekPipelineListener Interface Reference

Allows for callbacks between [SeekPipeline](#) objects when a [SeekImage](#) is ready for processing.

Inheritance diagram for com.thermal.seekware.SeekPipelineListener:



### Public Member Functions

- void [onImageSent](#) ([SeekImage](#) image)

#### 8.26.1 Detailed Description

Allows for callbacks between [SeekPipeline](#) objects when a [SeekImage](#) is ready for processing.

#### 8.26.2 Member Function Documentation

##### 8.26.2.1 `onImageSent()`

```
void com.thermal.seekware.SeekPipelineListener.onImageSent (
    SeekImage image )
```

Callback for seekPipeline.sendImage()



## Parameters

<i>image</i>	the <a href="#">SeekImage</a> associated with the callback
--------------	--

Implemented in [com.thermal.seekware.SeekPipeline](#), [com.thermal.seekware.SeekImageView](#), and [com.thermal.seekware.SeekImage](#)

The documentation for this interface was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekPipelineListener.java`

## 8.27 com.thermal.seekware.SeekUtility Class Reference

Contains utility classes, functions, for use with this SDK.

### Classes

- class [OrientationManager](#)  
*Manages orientation of the devices and rotation of views and overlays.*
- class [PermissionHandler](#)  
*Handles Android 6+ permissions.*
- class [Temperature](#)  
*Represents an immutable temperature with a value and a unit.*

### Static Public Member Functions

- static void [saveByteArray](#) (String filename, byte[] data)
- static void [saveByteBufferAsPrivateRaw](#) (@NonNull ByteBuffer data, @NonNull String filename, @NonNull Context context)
- static String [generateFilename](#) ()
- static Bitmap [bitmapFromUri](#) (@NonNull Uri uri, @NonNull Context context)
- static Bitmap [getBitmapFromDrawable](#) (Context context, int drawableId) throws IllegalArgumentException
- static Bitmap [overlayBitmapToCenter](#) (@NonNull Bitmap bitmap1, @NonNull Bitmap bitmap2)
- static Bitmap [createVideoThumbnail](#) (@NonNull Uri uri, @NonNull Context context, @NonNull Size size)
- static Bitmap [resizeBitmap](#) (@NonNull Bitmap image, int maxWidth, int maxHeight)
- static Bitmap [createSquaredBitmap](#) (@NonNull Bitmap source)
- static Bitmap [rotateBitmap](#) (@NonNull Bitmap source, float angle)
- static Bitmap [flipBitmapHorizontal](#) (@NonNull Bitmap source)
- static Bitmap [flipBitmapVertical](#) (@NonNull Bitmap source)
- static ArrayList< String > [findFirmwareUpgradeFiles](#) (Context context, String type)
- static String [enumNameToString](#) (String enumName)
- static float [distance](#) (Point p1, Point p2)
- static int [closest](#) (float val, int... candidates)
- static ByteBuffer [allocateByteBuffer](#) (int bytes)
- static byte[] [byteArrayFromFile](#) (String filename, Context context) throws IOException
- static ByteBuffer [byteBufferFromFile](#) (String filename, Context context) throws IOException
- static int [getDeviceDefaultOrientation](#) (Context context)

### 8.27.1 Detailed Description

Contains utility classes, functions, for use with this SDK.

### 8.27.2 Member Function Documentation

#### 8.27.2.1 allocateByteBuffer()

```
static ByteBuffer com.thermal.seekware.SeekUtility.allocateByteBuffer (
    int bytes ) [static]
```

Allocates a ByteBuffer suitable for use with SeekCameras

##### Parameters

<i>bytes</i>	number of bytes to allocate
--------------	-----------------------------

##### Returns

an allocated ByteBuffer in little endian order

#### 8.27.2.2 bitmapFromUri()

```
static Bitmap com.thermal.seekware.SeekUtility.bitmapFromUri (
    @NonNull Uri uri,
    @NonNull Context context ) [static]
```

Creates a bitmap from the given uri or returns null upon failure

##### Parameters

<i>uri</i>	desired uri
<i>context</i>	application context

##### Returns

bitmap from the given uri

#### 8.27.2.3 byteArrayFromFile()

```
static byte [] com.thermal.seekware.SeekUtility.byteArrayFromFile (
    String filename,
    Context context ) throws IOException [static]
```

Reads a .raw file into a byte array and returns it.

#### Parameters

<i>filename</i>	the file to read in assets
<i>context</i>	application context
<i>size</i>	size of the ByteBuffer

#### Returns

a ByteBuffer with the data from the file

#### 8.27.2.4 `byteBufferFromFile()`

```
static ByteBuffer com.thermal.seekware.SeekUtility.byteBufferFromFile (
    String filename,
    Context context ) throws IOException [static]
```

Reads a .raw file into a ByteBuffer and returns it.

#### Parameters

<i>filename</i>	the file to read
<i>context</i>	application context
<i>size</i>	size of the ByteBuffer

#### Returns

a ByteBuffer with the data from the file

#### 8.27.2.5 `closest()`

```
static int com.thermal.seekware.SeekUtility.closest (
    float val,
    int... candidates ) [static]
```

Returns the closest candidate to the given value

#### Parameters

<i>val</i>	value to compare against candidates
<i>candidates</i>	any number of candidates to check

**Returns**

the closest candidate to the given value

**8.27.2.6 createSquaredBitmap()**

```
static Bitmap com.thermal.seekware.SeekUtility.createSquaredBitmap (  
    @NonNull Bitmap source ) [static]
```

Creates a square bitmap from the source bitmap.

**Returns**

a square bitmap

**8.27.2.7 createVideoThumbnail()**

```
static Bitmap com.thermal.seekware.SeekUtility.createVideoThumbnail (  
    @NonNull Uri uri,  
    @NonNull Context context,  
    @NonNull Size size ) [static]
```

Creates a video thumbnail with a play icon overlay.

**Parameters**

<i>uri</i>	video uri to generate thumbnail for
<i>context</i>	application context
<i>size</i>	size of the thumbnail in pixels

**Returns**

a bitmap of the video thumbnail

**8.27.2.8 distance()**

```
static float com.thermal.seekware.SeekUtility.distance (  
    Point p1,  
    Point p2 ) [static]
```

Calculates the distance between two points and returns it

## Parameters

<i>p1</i>	first point
<i>p2</i>	second point

## Returns

the distance between the two points

**8.27.2.9 enumNameToString()**

```
static String com.thermal.seekware.SeekUtility.enumNameToString (
    String enumName ) [static]
```

Takes an enum name, converts it to a more readable format, and returns it For example, enum COLOR\_LUT will return "Color lut"

## Parameters

<i>enumName</i>	enum.name() of the enum to convert
-----------------	------------------------------------

## Returns

String representing a cleaned up version of the enum name

**8.27.2.10 findFirmwareUpgradeFiles()**

```
static ArrayList<String> com.thermal.seekware.SeekUtility.findFirmwareUpgradeFiles (
    Context context,
    String type ) [static]
```

Generates a list of firmware upgrade files found in assets

## Parameters

<i>context</i>	application context
<i>type</i>	type of file to search for (start of name)

## Returns

a list of firmware upgrade files

### 8.27.2.11 flipBitmapHorizontal()

```
static Bitmap com.thermal.seekware.SeekUtility.flipBitmapHorizontal (
    @NonNull Bitmap source ) [static]
```

Flips the source bitmap horizontally.

#### Returns

the source bitmap flipped horizontally

### 8.27.2.12 flipBitmapVertical()

```
static Bitmap com.thermal.seekware.SeekUtility.flipBitmapVertical (
    @NonNull Bitmap source ) [static]
```

Flips the source bitmap vertically.

#### Returns

the source bitmap flipped vertically

### 8.27.2.13 generateFilename()

```
static String com.thermal.seekware.SeekUtility.generateFilename ( ) [static]
```

Generates a default file name Format: IR\_yyyyMMdd\_HHmms

#### Returns

the generated file name

### 8.27.2.14 getBitmapFromDrawable()

```
static Bitmap com.thermal.seekware.SeekUtility.getBitmapFromDrawable (
    Context context,
    int drawableId ) throws IllegalArgumentException [static]
```

Finds a drawable in the application resources and converts it to a bitmap.

#### Parameters

<i>context</i>	application context
<i>drawableId</i>	id of the drawable to convert

**Returns**

a bitmap of the drawable

**8.27.2.15   getDeviceDefaultOrientation()**

```
static int com.thermal.seekware.SeekUtility.getDeviceDefaultOrientation (
    Context context ) [static]
```

Gets the device's default orientation and returns it

**Parameters**

<i>context</i>	application context
----------------	---------------------

**Returns**

the device's default orientation

**8.27.2.16   overlayBitmapToCenter()**

```
static Bitmap com.thermal.seekware.SeekUtility.overlayBitmapToCenter (
    @NonNull Bitmap bitmap1,
    @NonNull Bitmap bitmap2 ) [static]
```

Overlays bitmap2 into bitmap1.

**Parameters**

<i>bitmap1</i>	bitmap to draw into
<i>bitmap2</i>	bitmap to draw

**Returns**

a new bitmap with bitmap2 overlaid into bitmap1

**8.27.2.17   resizeBitmap()**

```
static Bitmap com.thermal.seekware.SeekUtility.resizeBitmap (
    @NonNull Bitmap image,
    int maxWidth,
    int maxHeight ) [static]
```

Resizes a bitmap to the given width and height.

**Parameters**

<i>image</i>	desired bitmap to resize
<i>maxWidth</i>	max width to rescale to
<i>maxHeight</i>	max height to rescale to

**Returns**

scaled bitmap

**8.27.2.18 rotateBitmap()**

```
static Bitmap com.thermal.seekware.SeekUtility.rotateBitmap (  
    @NonNull Bitmap source,  
    float angle ) [static]
```

Rotates the source bitmap by the given angle.

**Returns**

the source bitmap rotated by the given angle

**8.27.2.19 saveByteArray()**

```
static void com.thermal.seekware.SeekUtility.saveByteArray (  
    String filename,  
    byte[] data ) [static]
```

Writes the given binary frame to the given file name

**Parameters**

<i>filename</i>	the desired filename
<i>data</i>	the desired frame

**8.27.2.20 saveByteBufferAsPrivateRaw()**

```
static void com.thermal.seekware.SeekUtility.saveByteBufferAsPrivateRaw (  
    @NonNull ByteBuffer data,  
    @NonNull String filename,  
    @NonNull Context context ) [static]
```

Writes the given binary frame to the given file name



## Parameters

<i>data</i>	the desired frame
<i>filename</i>	the desired filename
<i>context</i>	application context

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekUtility.java

## 8.28 com.thermal.seekware.SeekCamera.State Enum Reference

The current state of the camera.

### Public Member Functions

- boolean [isAtLeast](#) (@NonNull [State](#) state)

### Public Attributes

- [INITIALIZED](#)
- [OPENED](#)
- [STARTED](#)
- [STOPPED](#)
- [CLOSED](#)

### 8.28.1 Detailed Description

The current state of the camera.

In general, the basic lifecycle of a [SeekCamera](#) looks like this: Initialized -> Open -> Started <--> Stopped -> Closed

### 8.28.2 Member Function Documentation

#### 8.28.2.1 isAtLeast()

```
boolean com.thermal.seekware.SeekCamera.State.isAtLeast (  
    @NonNull State state )
```

< Closed Compares the current state to given state and returns whether or not the current state is at least the given one Meant to mirror the call to LifecycleOwner's isAtLeast function

**Parameters**

<i>state</i>	state to compare to
--------------	---------------------

**Returns**

whether or not the state is at least the given state

### 8.28.3 Member Data Documentation

#### 8.28.3.1 CLOSED

```
com.thermal.seekware.SeekCamera.State.CLOSED
```

Set at the end of [close\(\)](#)

#### 8.28.3.2 INITIALIZED

```
com.thermal.seekware.SeekCamera.State.INITIALIZED
```

Set at the end of the constructor Initialized

#### 8.28.3.3 OPENED

```
com.thermal.seekware.SeekCamera.State.OPENED
```

Set at the end of [open\(\)](#) Opened

#### 8.28.3.4 STARTED

```
com.thermal.seekware.SeekCamera.State.STARTED
```

Set at the end of [start\(\)](#) Started

#### 8.28.3.5 STOPPED

```
com.thermal.seekware.SeekCamera.State.STOPPED
```

Set at the end of [stop\(\)](#) Stopped

The documentation for this enum was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekCamera.java`

## 8.29 com.thermal.seekware.SeekUtility.PermissionHandler.StateCallback Interface Reference

Callback for when a permission is granted.

### 8.29.1 Detailed Description

Callback for when a permission is granted.

The documentation for this interface was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekUtility.java

## 8.30 com.thermal.seekware.SeekCamera.StateCallback Interface Reference

Allows for callbacks to the states of the camera.

### Public Member Functions

- void [onInitialized](#) ([SeekCamera](#) camera)
- void [onOpened](#) ([SeekCamera](#) camera)
- void [onStarted](#) ([SeekCamera](#) camera)
- void [onStopped](#) ([SeekCamera](#) camera)
- void [onClosed](#) ([SeekCamera](#) camera)
- void [onMemoryAccess](#) ([SeekCamera](#) camera, [MemoryRegion](#) region, int progress)
- void [onReboot](#) ([SeekCamera](#) seekCamera)
- void [onError](#) ([SeekCamera](#) camera, Exception e)

### 8.30.1 Detailed Description

Allows for callbacks to the states of the camera.

This interface allows for callbacks to certain events of a [SeekCamera](#). Meant to mimic the interface [CameraDevice.StateCallback](#) from the camera2 API. NOTE: You must add the listener with the function [addListener\(StateCallback stateCallback\)](#) in order for the callbacks to work properly.

### 8.30.2 Member Function Documentation

#### 8.30.2.1 onClosed()

```
void com.thermal.seekware.SeekCamera.StateCallback.onClosed (  
    SeekCamera camera )
```

Called after the camera is closed.

## Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
---------------	---

**8.30.2.2 onError()**

```
void com.thermal.seekware.SeekCamera.StateCallback.onError (
    SeekCamera camera,
    Exception e )
```

Called when an error occurs involving the state of the camera. Exceptions that are generated will not be thrown, but instead passed to this callback. Functions that call `onError` will also return, as if an error has been thrown and caught.

## Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
<i>e</i>	Exception thrown

**8.30.2.3 onInitialized()**

```
void com.thermal.seekware.SeekCamera.StateCallback.onInitialized (
    SeekCamera camera )
```

Called after the camera is initialized.

## Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
---------------	---

**8.30.2.4 onMemoryAccess()**

```
void com.thermal.seekware.SeekCamera.StateCallback.onMemoryAccess (
    SeekCamera camera,
    MemoryRegion region,
    int progress )
```

Sends progress updates during a firmware memory read/write.

## Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
<i>region</i>	the <a href="#">MemoryRegion</a> that was accessed
<i>progress</i>	the percent completion of the memory read/write

### 8.30.2.5 onOpened()

```
void com.thermal.seekware.SeekCamera.StateCallback.onOpened (
    SeekCamera camera )
```

Called after the camera is opened.

#### Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
---------------	---

### 8.30.2.6 onReboot()

```
void com.thermal.seekware.SeekCamera.StateCallback.onReboot (
    SeekCamera seekCamera )
```

Called when a reboot of the camera is requested

#### Parameters

<i>seekCamera</i>	the <a href="#">SeekCamera</a> associated with the callback
-------------------	---

### 8.30.2.7 onStarted()

```
void com.thermal.seekware.SeekCamera.StateCallback.onStarted (
    SeekCamera camera )
```

Called after the camera is started.

#### Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
---------------	---

### 8.30.2.8 onStopped()

```
void com.thermal.seekware.SeekCamera.StateCallback.onStopped (
    SeekCamera camera )
```

Called after the camera is stopped.

## Parameters

<i>camera</i>	the <a href="#">SeekCamera</a> associated with the callback
---------------	---

The documentation for this interface was generated from the following file:

- `seekware/src/main/java/com/thermal/seekware/SeekCamera.java`

## 8.31 com.thermal.seekware.SeekUtility.Temperature Class Reference

Represents an immutable temperature with a value and a unit.

### Classes

- enum [Unit](#)  
*Represents a temperature unit (C, F or K)*

### Public Member Functions

- [Temperature](#) (float value, [Unit](#) unit)
- [Temperature](#) (float value)
- void [setUnit](#) ([Unit](#) unit)
- [Unit](#) [getUnit](#) ()
- float [getValue](#) ()

#### 8.31.1 Detailed Description

Represents an immutable temperature with a value and a unit.

This class represents a temperature with a value and a unit and allows for automatic conversion between different units with the `convertTemperature(unit)` function.

#### 8.31.2 Constructor & Destructor Documentation

##### 8.31.2.1 Temperature() [1/2]

```
com.thermal.seekware.SeekUtility.Temperature.Temperature (
    float value,
    Unit unit )
```

Initializer Constructor

## Parameters

<i>value</i>	the initial temperature value
<i>unit</i>	the initial temperature unit

**8.31.2.2 Temperature()** [2/2]

```
com.thermal.seekware.SeekUtility.Temperature.Temperature (
    float value )
```

Partial Initializer Constructor

## Parameters

<i>value</i>	the initial temperature value in degrees Celsius.
--------------	---

**8.31.3 Member Function Documentation****8.31.3.1 getUnit()**

```
Unit com.thermal.seekware.SeekUtility.Temperature.getUnit ( )
```

Gets the current units used to compute a temperature value.

Returns

the temperature unit

**8.31.3.2 getValue()**

```
float com.thermal.seekware.SeekUtility.Temperature.getValue ( )
```

Gets the current temperature value based on the current units.

Returns

the temperature unit

**8.31.3.3 setUnit()**

```
void com.thermal.seekware.SeekUtility.Temperature.setUnit (
    Unit unit )
```

Sets the units used to compute value.

## Parameters

<i>unit</i>	the desired temperature units
-------------	-------------------------------

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekUtility.java

## 8.32 com.thermal.seekware.Thermography Class Reference

Holds thermography data from a [SeekCamera](#).

### Classes

- class [Metrics](#)  
*Simple struct to hold average, min, and max temperatures.*

### Public Member Functions

- ByteBuffer [getBuffer](#) ()
- SeekUtility.Temperature [getSpotTemp](#) ()
- SeekUtility.Temperature [getMinTemp](#) ()
- SeekUtility.Temperature [getMaxTemp](#) ()
- Point [getMinPoint](#) ()
- Point [getMaxPoint](#) ()
- SeekUtility.Temperature [calcSpotTemperature](#) (Point point, int diameter)
- [Metrics](#) [calcSpotMetrics](#) (Point point, int diameter)
- SeekUtility.Temperature [calcAreaTemperature](#) (Point point, int width, int height)
- [Metrics](#) [calcAreaMetrics](#) (Point point, int width, int height)
- int [calculateIndex](#) (int x, int y)
- SeekUtility.Temperature [getPointTemperature](#) (Point point)

### Static Public Member Functions

- static float [fromShort](#) (short shortTemp)
- static [Thermography](#) [fromFile](#) (@NonNull String bufferFilename, @NonNull ExifInterface exifInterface, @NonNull Context context)

### Static Public Attributes

- static final int [THERMOGRAPHY\\_SCALE](#) = 64
- static final int [THERMOGRAPHY\\_OFFSET](#) = 40

#### 8.32.1 Detailed Description

Holds thermography data from a [SeekCamera](#).



## 8.32.2 Member Function Documentation

### 8.32.2.1 calcAreaMetrics()

```
Metrics com.thermal.seekware.Thermography.calcAreaMetrics (
    Point point,
    int width,
    int height )
```

Calculates the average, min, and max temperature of the given rectangle.

#### Parameters

<i>point</i>	(x,y) coordinates of the center of the rectangle
<i>width</i>	width of the rectangle
<i>height</i>	height of the rectangle

#### Returns

the metrics of the given rectangle

### 8.32.2.2 calcAreaTemperature()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.calcAreaTemperature (
    Point point,
    int width,
    int height )
```

Calculates the area temperature of the given rectangle. The same calculation as [Thermography#calcSpotTemperature\(Point, int\)](#), but allows for any rectangle rather than only squares.

#### Parameters

<i>point</i>	x,y) coordinates of the center of the area
<i>width</i>	width of the rectangle to average
<i>height</i>	height of the rectangle to average

#### Returns

average temperature of the rectangle

### 8.32.2.3 calcSpotMetrics()

```
Metrics com.thermal.seekware.Thermography.calcSpotMetrics (
    Point point,
    int diameter )
```

Equivalent to [Thermography#calcAreaMetrics\(Point, int, int\)](#) with width and height as diameter.

#### Parameters

<i>point</i>	(x,y) coordinates of the center of the spot
<i>diameter</i>	diameter of the square

#### Returns

average, min, and max temperature of the diameter grid of pixels

### 8.32.2.4 calcSpotTemperature()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.calcSpotTemperature (
    Point point,
    int diameter )
```

Calculates the spot temperature based on the given parameters

#### Pixel Average Diagram

**Table 8.90 1 x 1 Pixel Average**

	x-2	x-1	x	x+1	x+2	x+3
y-2						
y-1						
y			*			
y+1						
y+2						
y+3						

**Table 8.91 2 x 2 Pixel Average**

	x-2	x-1	x	x+1	x+2	x+3
y-2						
y-1						
y			*	*		
y+1			*	*		
y+2						
y+3						

Table 8.92 3 x 3 Pixel Average

	x-2	x-1	x	x+1	x+2	x+3
y-2						
y-1		*	*	*		
y		*	*	*		
y+1		*	*	*		
y+2						
y+3						

Table 8.93 4 x 4 Pixel Average

	x-2	x-1	x	x+1	x+2	x+3
y-2						
y-1		*	*	*	*	
y		*	*	*	*	
y+1		*	*	*	*	
y+2		*	*	*	*	
y+3						

**Parameters**

<i>point</i>	(x,y) coordinates of the center of the spot
<i>diameter</i>	diameter to average

**Returns**

average temperature of the diameter grid of pixels

**8.32.2.5 calculateIndex()**

```
int com.thermal.seekware.Thermography.calculateIndex (
    int x,
    int y )
```

Calculates a flattened index from x, y (column, row) coordinates

**Parameters**

<i>x</i>	horizontal (column) coordinate
<i>y</i>	vertical (row) coordinate

**Returns**

integer index value

### 8.32.2.6 fromFile()

```
static Thermography com.thermal.seekware.Thermography.fromFile (
    @NonNull String bufferFilename,
    @NonNull ExifInterface exifInterface,
    @NonNull Context context ) [static]
```

Creates a thermography object based on the given files

#### Parameters

<i>bufferFilename</i>	the file of the thermography buffer (.raw file)
<i>exifInterface</i>	Exif tags with thermography data
<i>context</i>	application context

#### Returns

[Thermography](#) with parameters generated from the files

### 8.32.2.7 fromShort()

```
static float com.thermal.seekware.Thermography.fromShort (
    short shortTemp ) [static]
```

Converts a short temp into a float value

#### Parameters

<i>shortTemp</i>	short temp
------------------	------------

#### Returns

float value

### 8.32.2.8 getBuffer()

```
ByteBuffer com.thermal.seekware.Thermography.getBuffer ( )
```

Returns a ByteBuffer of the thermography values. In order to get a floating point value out of this buffer at (x, y), the following steps need to be taken:

1. Calculate the corrected point by using [SeekCamera.Characteristics#getOrientation\(\)](#).
2. convert the ByteBuffer returned here to a short buffer ([getBuffer\(\)](#).asShortBuffer()).

3. flatten the 2D Point using `calculateIndex(int, int)`.
4. Get the short value out of the short buffer (`getBuffer().asShortBuffer().get(index)`).
5. Convert it to a float with `fromShort(short)`.
6. The float value is now ready to use.

**Returns**

a ByteBuffer of the thermography values

**8.32.2.9 getMaxPoint()**

```
Point com.thermal.seekware.Thermography.getMaxPoint ( )
```

Returns a Point of where the hottest coordinate is located.

**Returns**

a Point of where the hottest coordinate is located

**8.32.2.10 getMaxTemp()**

```
SeekUtility.Temperature com.thermal.seekware.Thermography.getMaxTemp ( )
```

Gets the 5x5 average temperature around the hottest pixel coordinate in the image. This is equivalent to calling `calcSpotTemperature(Point, int)` with `getMaxPoint()` and 5.

**Returns**

the 5x5 average temperature around the hottest pixel coordinate

**8.32.2.11 getMinPoint()**

```
Point com.thermal.seekware.Thermography.getMinPoint ( )
```

Returns a Point of where the coldest coordinate is located.

**Returns**

a Point of where the coldest coordinate is located

### 8.32.2.12 getMinTemp()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.getMinTemp ( )
```

Gets the 5x5 average temperature around the coldest pixel coordinate in the image. This is equivalent calling [calcSpotTemperature\(Point, int\)](#) with [getMinPoint\(\)](#) and 5.

#### Returns

the 5x5 average temperature around the coldest pixel coordinate

### 8.32.2.13 getPointTemperature()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.getPointTemperature (
    Point point )
```

Gets the point temperature based on the given parameters

#### Parameters

<i>point</i>	(x,y) coordinates of the center of the spot
--------------	---

#### Returns

temperature of the given point

### 8.32.2.14 getSpotTemp()

```
SeekUtility.Temperature com.thermal.seekware.Thermography.getSpotTemp ( )
```

Gets the 6x6 average temperature around the center pixel coordinate and returns it. This is equivalent to calling [calcSpotTemperature\(Point, int\)](#) with new [Point\(SeekCamera.Characteristics#getWidth\(\) / 2, SeekCamera.Characteristics#getHeight\(\) / 2\)](#) and 6.

#### Returns

the 6x6 average temperature around the center pixel coordinate

## 8.32.3 Member Data Documentation

#### 8.32.3.1 THERMOGRAPHY\_OFFSET

```
final int com.thermal.seekware.Thermography.THERMOGRAPHY_OFFSET = 40 [static]
```

The thermography offset used when converting to a float

#### 8.32.3.2 THERMOGRAPHY\_SCALE

```
final int com.thermal.seekware.Thermography.THERMOGRAPHY_SCALE = 64 [static]
```

The thermography scale used when converting to a float

The documentation for this class was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/Thermography.java

## 8.33 com.thermal.seekware.SeekUtility.Temperature.Unit Enum Reference

Represents a temperature unit (C, F or K)

### Public Attributes

- [CELSIUS](#)
- [FAHRENHEIT](#)
- [KELVIN](#)

#### 8.33.1 Detailed Description

Represents a temperature unit (C, F or K)

This enum represents the units of a [Temperature](#).

#### 8.33.2 Member Data Documentation

##### 8.33.2.1 CELSIUS

```
com.thermal.seekware.SeekUtility.Temperature.Unit.CELSIUS
```

Celsius (C)

##### 8.33.2.2 FAHRENHEIT

```
com.thermal.seekware.SeekUtility.Temperature.Unit.FAHRENHEIT
```

Fahrenheit (F)

##### 8.33.2.3 KELVIN

```
com.thermal.seekware.SeekUtility.Temperature.Unit.KELVIN
```

Kelvin (K)

The documentation for this enum was generated from the following file:

- seekware/src/main/java/com/thermal/seekware/SeekUtility.java





# Index

- addTagFilters
  - com.thermal.seekware.SeekLogger, 97
- addViews
  - com.thermal.seekware.SeekUtility.OrientationManager, 73
- ALL
  - com.thermal.seekware.SeekLogger, 99
- allocateByteBuffer
  - com.thermal.seekware.SeekUtility, 104
- AMBER
  - com.thermal.seekware.SeekCamera.ColorLut, 58
- AUTO
  - com.thermal.seekware.SeekCamera.AspectRatio, 46
- BACK
  - com.thermal.seekware.SeekCamera.LensFacing, 66
- bitmapFromUri
  - com.thermal.seekware.SeekUtility, 104
- BLACK\_RECON
  - com.thermal.seekware.SeekCamera.ColorLut, 59
- BLACKHOT
  - com.thermal.seekware.SeekCamera.ColorLut, 59
- byteArrayFromFile
  - com.thermal.seekware.SeekUtility, 104
- byteBufferFromFile
  - com.thermal.seekware.SeekUtility, 105
- calcAreaMetrics
  - com.thermal.seekware.Thermography, 119
- calcAreaTemperature
  - com.thermal.seekware.Thermography, 119
- calcSpotMetrics
  - com.thermal.seekware.Thermography, 119
- calcSpotTemperature
  - com.thermal.seekware.Thermography, 120
- calculateIndex
  - com.thermal.seekware.Thermography, 121
- CELSIUS
  - com.thermal.seekware.SeekUtility.Temperature.Unit, 125
- close
  - com.thermal.seekware.SeekCamera, 77
- CLOSED
  - com.thermal.seekware.SeekCamera.State, 112
- closest
  - com.thermal.seekware.SeekUtility, 105
- com.thermal.seekware.SeekCamera, 75
  - close, 77
- createSeekCameraCaptureSession, 78
- getAspectRatio, 78
- getCharacteristics, 78
- getChipId, 79
- getColorLut, 79
- getColorLutName, 79
- getColorPalette, 79, 80
- getCurrentState, 80
- getEmissivity, 80
- getImageSmoothing, 80
- loadUserLutData, 81
- memoryRead, 81, 82
- memoryWrite, 82, 83
- open, 83
- reboot, 84
- resumeShutter, 84
- setAGCMode, 84
- setAspectRatio, 84
- setColorLut, 84
- setEmissivity, 85
- setImageSmoothing, 85
- setSeekExceptionListener, 85
- start, 86
- stop, 86
- suspendShutter, 86
- toString, 86
- triggerShutter, 86
- upgradeFirmware, 87
- com.thermal.seekware.SeekCamera.AGCMode, 45
  - HISTEQ, 45
  - LEGACY\_HISTEQ, 45
  - LINEAR, 45
- com.thermal.seekware.SeekCamera.AspectRatio, 46
  - AUTO, 46
  - MATCH\_HEIGHT, 48
  - MATCH\_WIDTH, 50
- com.thermal.seekware.SeekCamera.Characteristics, 52
  - convertScreenToSensorPoint, 53
  - convertSensorToScreenPoint, 53
  - getCorrectedOrientation, 54
  - getFirmwareVersion, 54
  - getHeight, 54
  - getLensFacing, 54
  - getModelNumber, 55
  - getOrientation, 55
  - getSensorOrientation, 55
  - getSerialNumber, 55
  - getTemperatureUnit, 56
  - getWidth, 56

- setLensFacing, 56
  - setOrientation, 57
  - setTemperatureUnit, 57
- com.thermal.seekware.SeekCamera.ColorLut, 57
  - AMBER, 58
  - BLACK\_RECON, 59
  - BLACKHOT, 59
  - createUserLut, 58
  - GREEN, 59
  - HI, 59
  - HILO, 60
  - IRON, 60
  - IRON2, 60
  - PRISM, 60
  - RECON, 61
  - SPECTRA, 61
  - TYRIAN, 61
  - USER0, 61
  - USER1, 62
  - USER2, 62
  - USER3, 62
  - USER4, 62
  - WHITEHOT, 63
- com.thermal.seekware.SeekCamera.LensFacing, 66
  - BACK, 66
  - FRONT, 66
- com.thermal.seekware.SeekCamera.MemoryRegion, 67
  - IMAGE0, 67
  - IMAGE1, 67
  - NEW\_IMAGE, 67
- com.thermal.seekware.SeekCamera.Orientation, 71
  - getCorrectedOrientation, 71
  - next, 71
  - ORIENTATION\_0, 72
  - ORIENTATION\_180, 72
  - ORIENTATION\_270, 72
  - ORIENTATION\_90, 72
  - previous, 72
- com.thermal.seekware.SeekCamera.SeekExceptionListener, 89
  - onSeekIOException, 89
- com.thermal.seekware.SeekCamera.State, 111
  - CLOSED, 112
  - INITIALIZED, 112
  - isAtLeast, 111
  - OPENED, 112
  - STARTED, 112
  - STOPPED, 112
- com.thermal.seekware.SeekCamera.StateCallback, 113
  - onClosed, 113
  - onError, 114
  - onInitialized, 114
  - onMemoryAccess, 114
  - onOpened, 115
  - onReboot, 115
  - onStarted, 115
  - onStopped, 115
- com.thermal.seekware.SeekCameraManager, 87
  - context, 89
  - getUSBDeviceCount, 88
  - SeekCameraManager, 88
- com.thermal.seekware.SeekImage, 90
  - getColorBitmap, 90
  - getColorsUsed, 90
  - getFilteredBuffer, 91
  - getThermography, 91
- com.thermal.seekware.SeekImageReader, 91
  - onImageSent, 92
  - SeekImageReader, 92
  - setOnImageAvailableListener, 93
- com.thermal.seekware.SeekImageReader.OnImageAvailableListener, 70
  - onImageAvailable, 70
- com.thermal.seekware.SeekImageView, 93
  - onImageSent, 95
  - SeekImageView, 94
  - setInput, 95
  - setOnFrameAvailableListener, 95
- com.thermal.seekware.SeekImageView.OnFrameAvailableListener, 69
  - onFrameAvailable, 69
- com.thermal.seekware.SeekIOException, 96
- com.thermal.seekware.SeekIOException.ErrorCode, 63
  - contains, 63
  - get, 64
  - value, 64
- com.thermal.seekware.SeekLogger, 96
  - addTagFilters, 97
  - ALL, 99
  - debug, 97
  - error, 97
  - info, 98
  - NONE, 99
  - setFilter, 98
  - verbose, 98
  - warn, 99
- com.thermal.seekware.SeekPipeline, 100
  - image, 101
  - input, 101
  - onImageSent, 100
- com.thermal.seekware.SeekPipelineException, 101
  - getErrorCode, 102
- com.thermal.seekware.SeekPipelineException.ErrorCode, 64
  - contains, 65
  - get, 65
  - value, 66
- com.thermal.seekware.SeekPipelineListener, 102
  - onImageSent, 102
- com.thermal.seekware.SeekUtility, 103
  - allocateByteBuffer, 104
  - bitmapFromUri, 104
  - byteArrayFromFile, 104
  - byteBufferFromFile, 105

- closest, [105](#)
- createSquaredBitmap, [106](#)
- createVideoThumbnail, [106](#)
- distance, [106](#)
- enumNameToString, [107](#)
- findFirmwareUpgradeFiles, [107](#)
- flipBitmapHorizontal, [107](#)
- flipBitmapVertical, [108](#)
- generateFilename, [108](#)
- getBitmapFromDrawable, [108](#)
- getDeviceDefaultOrientation, [109](#)
- overlayBitmapToCenter, [109](#)
- resizeBitmap, [109](#)
- rotateBitmap, [110](#)
- saveByteArray, [110](#)
- saveByteBufferAsPrivateRaw, [110](#)
- com.thermal.seekware.SeekUtility.OrientationManager, [73](#)
  - addViews, [73](#)
  - getOrientation, [73](#)
  - getRawOrientation, [74](#)
- com.thermal.seekware.SeekUtility.PermissionHandler, [74](#)
- com.thermal.seekware.SeekUtility.PermissionHandler.Permission, [74](#)
- com.thermal.seekware.SeekUtility.PermissionHandler.StateCallback, [113](#)
- com.thermal.seekware.SeekUtility.Temperature, [116](#)
  - getUnit, [117](#)
  - getValue, [117](#)
  - setUnit, [117](#)
  - Temperature, [116](#), [117](#)
- com.thermal.seekware.SeekUtility.Temperature.Unit, [125](#)
  - CELSIUS, [125](#)
  - FAHRENHEIT, [125](#)
  - KELVIN, [125](#)
- com.thermal.seekware.Thermography, [118](#)
  - calcAreaMetrics, [119](#)
  - calcAreaTemperature, [119](#)
  - calcSpotMetrics, [119](#)
  - calcSpotTemperature, [120](#)
  - calculateIndex, [121](#)
  - fromFile, [121](#)
  - fromShort, [122](#)
  - getBuffer, [122](#)
  - getMaxPoint, [123](#)
  - getMaxTemp, [123](#)
  - getMinPoint, [123](#)
  - getMinTemp, [123](#)
  - getPointTemperature, [124](#)
  - getSpotTemp, [124](#)
  - THERMOGRAPHY\_OFFSET, [124](#)
  - THERMOGRAPHY\_SCALE, [125](#)
- com.thermal.seekware.Thermography.Metrics, [68](#)
  - getAverage, [68](#)
  - getMax, [68](#)
  - getMin, [69](#)
- contains
  - com.thermal.seekware.SeekIOException.ErrorCode, [63](#)
  - com.thermal.seekware.SeekPipelineException.ErrorCode, [65](#)
- context
  - com.thermal.seekware.SeekCameraManager, [89](#)
- convertScreenToSensorPoint
  - com.thermal.seekware.SeekCamera.Characteristics, [53](#)
- convertSensorToScreenPoint
  - com.thermal.seekware.SeekCamera.Characteristics, [53](#)
- createSeekCameraCaptureSession
  - com.thermal.seekware.SeekCamera, [78](#)
- createSquaredBitmap
  - com.thermal.seekware.SeekUtility, [106](#)
- createUserLut
  - com.thermal.seekware.SeekCamera.ColorLut, [58](#)
- createVideoThumbnail
  - com.thermal.seekware.SeekUtility, [106](#)
- debug
  - com.thermal.seekware.SeekLogger, [97](#)
- distance
  - com.thermal.seekware.SeekUtility, [106](#)
- enumNameToString
  - com.thermal.seekware.SeekUtility, [107](#)
- error
  - com.thermal.seekware.SeekLogger, [97](#)
- FAHRENHEIT
  - com.thermal.seekware.SeekUtility.Temperature.Unit, [125](#)
- findFirmwareUpgradeFiles
  - com.thermal.seekware.SeekUtility, [107](#)
- flipBitmapHorizontal
  - com.thermal.seekware.SeekUtility, [107](#)
- flipBitmapVertical
  - com.thermal.seekware.SeekUtility, [108](#)
- fromFile
  - com.thermal.seekware.Thermography, [121](#)
- fromShort
  - com.thermal.seekware.Thermography, [122](#)
- FRONT
  - com.thermal.seekware.SeekCamera.LensFacing, [66](#)
- generateFilename
  - com.thermal.seekware.SeekUtility, [108](#)
- get
  - com.thermal.seekware.SeekIOException.ErrorCode, [64](#)
  - com.thermal.seekware.SeekPipelineException.ErrorCode, [65](#)
- getAspectRatio
  - com.thermal.seekware.SeekCamera, [78](#)
- getAverage

- com.thermal.seekware.Thermography.Metrics, 68
- getBitmapFromDrawable
  - com.thermal.seekware.SeekUtility, 108
- getBuffer
  - com.thermal.seekware.Thermography, 122
- getCharacteristics
  - com.thermal.seekware.SeekCamera, 78
- getChipId
  - com.thermal.seekware.SeekCamera, 79
- getColorBitmap
  - com.thermal.seekware.SeekImage, 90
- getColorLut
  - com.thermal.seekware.SeekCamera, 79
- getColorLutName
  - com.thermal.seekware.SeekCamera, 79
- getColorPalette
  - com.thermal.seekware.SeekCamera, 79, 80
- getColorsUsed
  - com.thermal.seekware.SeekImage, 90
- getCorrectedOrientation
  - com.thermal.seekware.SeekCamera.Characteristics, 54
  - com.thermal.seekware.SeekCamera.Orientation, 71
- getCurrentState
  - com.thermal.seekware.SeekCamera, 80
- getDeviceDefaultOrientation
  - com.thermal.seekware.SeekUtility, 109
- getEmissivity
  - com.thermal.seekware.SeekCamera, 80
- getErrorCode
  - com.thermal.seekware.SeekPipelineException, 102
- getFilteredBuffer
  - com.thermal.seekware.SeekImage, 91
- getFirmwareVersion
  - com.thermal.seekware.SeekCamera.Characteristics, 54
- getHeight
  - com.thermal.seekware.SeekCamera.Characteristics, 54
- getImageSmoothing
  - com.thermal.seekware.SeekCamera, 80
- getLensFacing
  - com.thermal.seekware.SeekCamera.Characteristics, 54
- getMax
  - com.thermal.seekware.Thermography.Metrics, 68
- getMaxPoint
  - com.thermal.seekware.Thermography, 123
- getMaxTemp
  - com.thermal.seekware.Thermography, 123
- getMin
  - com.thermal.seekware.Thermography.Metrics, 69
- getMinPoint
  - com.thermal.seekware.Thermography, 123
- getMinTemp
  - com.thermal.seekware.Thermography, 123
- getModelNumber
  - com.thermal.seekware.SeekCamera.Characteristics, 55
- getOrientation
  - com.thermal.seekware.SeekCamera.Characteristics, 55
  - com.thermal.seekware.SeekUtility.OrientationManager, 73
- getPointTemperature
  - com.thermal.seekware.Thermography, 124
- getRawOrientation
  - com.thermal.seekware.SeekUtility.OrientationManager, 74
- getSensorOrientation
  - com.thermal.seekware.SeekCamera.Characteristics, 55
- getSerialNumber
  - com.thermal.seekware.SeekCamera.Characteristics, 55
- getSpotTemp
  - com.thermal.seekware.Thermography, 124
- getTemperatureUnit
  - com.thermal.seekware.SeekCamera.Characteristics, 56
- getThermography
  - com.thermal.seekware.SeekImage, 91
- getUnit
  - com.thermal.seekware.SeekUtility.Temperature, 117
- getUSBDeviceCount
  - com.thermal.seekware.SeekCameraManager, 88
- getValue
  - com.thermal.seekware.SeekUtility.Temperature, 117
- getWidth
  - com.thermal.seekware.SeekCamera.Characteristics, 56
- GREEN
  - com.thermal.seekware.SeekCamera.ColorLut, 59
- HI
  - com.thermal.seekware.SeekCamera.ColorLut, 59
- HILO
  - com.thermal.seekware.SeekCamera.ColorLut, 60
- HISTEQ
  - com.thermal.seekware.SeekCamera.AGCMode, 45
- image
  - com.thermal.seekware.SeekPipeline, 101
- IMAGE0
  - com.thermal.seekware.SeekCamera.MemoryRegion, 67
- IMAGE1
  - com.thermal.seekware.SeekCamera.MemoryRegion, 67
- info
  - com.thermal.seekware.SeekLogger, 98
- INITIALIZED

- com.thermal.seekware.SeekCamera.State, 112
- input
  - com.thermal.seekware.SeekPipeline, 101
- IRON
  - com.thermal.seekware.SeekCamera.ColorLut, 60
- IRON2
  - com.thermal.seekware.SeekCamera.ColorLut, 60
- isAtLeast
  - com.thermal.seekware.SeekCamera.State, 111
- KELVIN
  - com.thermal.seekware.SeekUtility.Temperature.Unit, 125
- LEGACY\_HISTEQ
  - com.thermal.seekware.SeekCamera.AGCMODE, 45
- LINEAR
  - com.thermal.seekware.SeekCamera.AGCMODE, 45
- loadUserLutData
  - com.thermal.seekware.SeekCamera, 81
- MATCH\_HEIGHT
  - com.thermal.seekware.SeekCamera.AspectRatio, 48
- MATCH\_WIDTH
  - com.thermal.seekware.SeekCamera.AspectRatio, 50
- memoryRead
  - com.thermal.seekware.SeekCamera, 81, 82
- memoryWrite
  - com.thermal.seekware.SeekCamera, 82, 83
- NEW\_IMAGE
  - com.thermal.seekware.SeekCamera.MemoryRegion, 67
- next
  - com.thermal.seekware.SeekCamera.Orientation, 71
- NONE
  - com.thermal.seekware.SeekLogger, 99
- onClosed
  - com.thermal.seekware.SeekCamera.StateCallback, 113
- onError
  - com.thermal.seekware.SeekCamera.StateCallback, 114
- onFrameAvailable
  - com.thermal.seekware.SeekImageView.OnFrameAvailableListener, 69
- onImageAvailable
  - com.thermal.seekware.SeekImageReader.OnImageAvailableListener, 70
- onImageSent
  - com.thermal.seekware.SeekImageReader, 92
  - com.thermal.seekware.SeekImageView, 95
  - com.thermal.seekware.SeekPipeline, 100
- com.thermal.seekware.SeekPipelineListener, 102
- onInitialized
  - com.thermal.seekware.SeekCamera.StateCallback, 114
- onMemoryAccess
  - com.thermal.seekware.SeekCamera.StateCallback, 114
- onOpened
  - com.thermal.seekware.SeekCamera.StateCallback, 115
- onReboot
  - com.thermal.seekware.SeekCamera.StateCallback, 115
- onSeekIOException
  - com.thermal.seekware.SeekCamera.SeekExceptionListener, 89
- onStarted
  - com.thermal.seekware.SeekCamera.StateCallback, 115
- onStopped
  - com.thermal.seekware.SeekCamera.StateCallback, 115
- open
  - com.thermal.seekware.SeekCamera, 83
- OPENED
  - com.thermal.seekware.SeekCamera.State, 112
- ORIENTATION\_0
  - com.thermal.seekware.SeekCamera.Orientation, 72
- ORIENTATION\_180
  - com.thermal.seekware.SeekCamera.Orientation, 72
- ORIENTATION\_270
  - com.thermal.seekware.SeekCamera.Orientation, 72
- ORIENTATION\_90
  - com.thermal.seekware.SeekCamera.Orientation, 72
- overlayBitmapToCenter
  - com.thermal.seekware.SeekUtility, 109
- previous
  - com.thermal.seekware.SeekCamera.Orientation, 72
- PRISM
  - com.thermal.seekware.SeekCamera.ColorLut, 60
- reboot
  - com.thermal.seekware.SeekCamera, 84
- RECON
  - com.thermal.seekware.SeekCamera.ColorLut, 61
- resizeBitmap
  - com.thermal.seekware.SeekUtility, 109
- resumeShutter
  - com.thermal.seekware.SeekCamera, 84
- rotateBitmap
  - com.thermal.seekware.SeekUtility, 110
- saveByteArray

- com.thermal.seekware.SeekUtility, 110
- saveByteBufferAsPrivateRaw
  - com.thermal.seekware.SeekUtility, 110
- SeekCameraManager
  - com.thermal.seekware.SeekCameraManager, 88
- SeekImageReader
  - com.thermal.seekware.SeekImageReader, 92
- SeekImageView
  - com.thermal.seekware.SeekImageView, 94
- setAGCMode
  - com.thermal.seekware.SeekCamera, 84
- setAspectRatio
  - com.thermal.seekware.SeekCamera, 84
- setColorLut
  - com.thermal.seekware.SeekCamera, 84
- setEmissivity
  - com.thermal.seekware.SeekCamera, 85
- setFilter
  - com.thermal.seekware.SeekLogger, 98
- setImageSmoothing
  - com.thermal.seekware.SeekCamera, 85
- setInput
  - com.thermal.seekware.SeekImageView, 95
- setLensFacing
  - com.thermal.seekware.SeekCamera.Characteristics, 56
- setOnFrameAvailableListener
  - com.thermal.seekware.SeekImageView, 95
- setOnImageAvailableListener
  - com.thermal.seekware.SeekImageReader, 93
- setOrientation
  - com.thermal.seekware.SeekCamera.Characteristics, 57
- setSeekExceptionHandler
  - com.thermal.seekware.SeekCamera, 85
- setTemperatureUnit
  - com.thermal.seekware.SeekCamera.Characteristics, 57
- setUnit
  - com.thermal.seekware.SeekUtility.Temperature, 117
- SPECTRA
  - com.thermal.seekware.SeekCamera.ColorLut, 61
- start
  - com.thermal.seekware.SeekCamera, 86
- STARTED
  - com.thermal.seekware.SeekCamera.State, 112
- stop
  - com.thermal.seekware.SeekCamera, 86
- STOPPED
  - com.thermal.seekware.SeekCamera.State, 112
- suspendShutter
  - com.thermal.seekware.SeekCamera, 86
- Temperature
  - com.thermal.seekware.SeekUtility.Temperature, 116, 117
- THERMOGRAPHY\_OFFSET
  - com.thermal.seekware.Thermography, 124
- THERMOGRAPHY\_SCALE
  - com.thermal.seekware.Thermography, 125
- toString
  - com.thermal.seekware.SeekCamera, 86
- triggerShutter
  - com.thermal.seekware.SeekCamera, 86
- TYRIAN
  - com.thermal.seekware.SeekCamera.ColorLut, 61
- upgradeFirmware
  - com.thermal.seekware.SeekCamera, 87
- USER0
  - com.thermal.seekware.SeekCamera.ColorLut, 61
- USER1
  - com.thermal.seekware.SeekCamera.ColorLut, 62
- USER2
  - com.thermal.seekware.SeekCamera.ColorLut, 62
- USER3
  - com.thermal.seekware.SeekCamera.ColorLut, 62
- USER4
  - com.thermal.seekware.SeekCamera.ColorLut, 62
- value
  - com.thermal.seekware.SeekIOException.ErrorCode, 64
  - com.thermal.seekware.SeekPipelineException.ErrorCode, 66
- verbose
  - com.thermal.seekware.SeekLogger, 98
- warn
  - com.thermal.seekware.SeekLogger, 99
- WHITEHOT
  - com.thermal.seekware.SeekCamera.ColorLut, 63